

如何重設Cisco Emergency Responder資料庫復寫

目錄

[簡介](#)

[必要條件](#)

[需求](#)

[採用元件](#)

[CER資料庫複製重置過程](#)

[摘要步驟](#)

[詳細步驟](#)

[從主伺服器的CLI中刪除cerremote表中的條目](#)

[從主伺服器和輔助伺服器的CLI重新啟動服務](#)

[從主伺服器的CLI重置複製](#)

[從輔助伺服器的CLI重新啟動伺服器](#)

[輔助節點處於完全服務狀態後檢查複製](#)

[如有必要，重複該過程](#)

簡介

本文檔介紹如何重置Cisco Emergency Responder(CER)資料庫複製。

必要條件

需求

本文件沒有特定需求。

採用元件

本檔案所述內容不限於特定軟體和硬體版本；但是，用於建立該文檔的版本是CER版本10。

本文中的資訊是根據特定實驗室環境內的裝置所建立。文中使用到的所有裝置皆從已清除（預設）的組態來啟動。如果您的網路正在作用，請確保您已瞭解任何指令可能造成的影響。

CER資料庫複製重置過程

摘要步驟

步驟1.使用CER主節點的命令列介面(CLI)刪除cerremote資料庫表上的條目。

步驟2.在主節點和輔助節點上重新啟動服務。

步驟3.從CER主節點的CLI重置複製。

步驟4.重新啟動輔助節點。

步驟5.檢查複製

步驟6.如有必要，重複該過程

詳細步驟

從主伺服器的CLI中刪除cerremote表中的條目

使用命令run sql delete from cerremote刪除cerremote資料庫表中的條目，然後使用命令run sql select name from cerremote確認cerremote表中沒有條目。

```
admin:run sql delete from cerremote
Rows: 4
admin:
```

```
admin:run sql select name from cerremote
name
====
admin:
```

從主伺服器和輔助伺服器的CLI重新啟動服務

使用以下命令重新啟動主節點和輔助節點上的服務：

- **utils service restart Cisco Emergency Responder**
- **utils service restart Cisco Tomcat**
- **utils服務重新啟動Cisco DB Replicator**
- **utils service restart Cisco IDS or utils service stop Cisco IDS and utils service start Cisco IDS**

```
admin:utils service restart Cisco Emergency Responder
Don't press Ctrl-c while the service is getting RESTARTED.If Service has not Restarted Properly, execute the same Command Again
Service Manager is running
Cisco Emergency Responder[STOPPING]
Commanded Out of Service
Cisco Emergency Responder[NOTRUNNING]
Service Manager is running
Cisco Emergency Responder[STARTING]
Cisco Emergency Responder[STARTING]
Cisco Emergency Responder[STARTED]
admin:
```

```
admin:utils service restart Cisco Tomcat
Don't press Ctrl-c while the service is getting RESTARTED.If Service has not Re
started Properly, execute the same Command Again
Service Manager is running
Cisco Tomcat[STOPPING]
Cisco Tomcat[STOPPING]
Commanded Out of Service
Cisco Tomcat[NOTRUNNING]
Service Manager is running
Cisco Tomcat[STARTING]
Cisco Tomcat[STARTING]
Cisco Tomcat[STARTED]
admin:□
```

```
admin:utils service restart A Cisco DB Replicator
Don't press Ctrl-c while the service is getting RESTARTED.If Service has not Restated Prope
rly, execute the same Command Again
Service Manager is running
Commanded Out of Service
A Cisco DB Replicator[NOTRUNNING]
Service Manager is running
A Cisco DB Replicator[STARTED]
admin:█
```

```
admin:utils service stop Cisco IDS
Service Manager is running
Cisco IDS[STOPPING]
Cisco IDS[STOPPING]
Commanded Out of Service
Cisco IDS[NOTRUNNING]
admin:utils service start Cisco IDS
Service Manager is running
Cisco IDS[STARTING]
Cisco IDS[STARTING]
Cisco IDS[STARTED]
admin:□
```

從主伺服器的CLI重置複製

從主節點的CLI使用命令utils dbremote reset all重置群集中的複製。

```
admin:utils dbreplication reset all
Replication reset is in progress.
Background repair of replication will continue after that for about 15 minutes.
Subscriber is CERSub
Please restart the Cisco ER Subscriber node from CUOS administration or using the CLI command
: 'utils system restart'
admin:□
```

從輔助伺服器的CLI重新啟動伺服器

一旦主節點上的重置完成，將顯示重新啟動輔助節點的提示。此時，使用命令utils system restart從

CLI重新啟動輔助控制器。

```
admin:utils system restart
Do you really want to restart ?
Enter (yes/no)? yes

Appliance is being Restarted ...
Warning: Restart could take up to 5 minutes.
Shutting down Service Manager. Please wait...
Manager shutting down services... Please Wait
```

輔助節點處於完全服務狀態後檢查複製

輔助伺服器處於完全服務狀態後，使用命令utils複製狀態從主伺服器的CLI檢查資料庫複製。

```
admin:utils dbreplication status

----- utils dbreplication status -----
Output is in file /var/log/active/er/trace/dbl/sdi/ReplicationStatus.2015_01_21_12_28_48.out
Please use "file view activelog er/trace/dbl/sdi/ReplicationStatus.2015_01_21_12_28_48.out " command to see the o
utput
admin:
```

status命令的輸出中有一個file view命令。使用file view命令確認沒有問題。

檔案檢視activelog er/trace/dbl/sdi/ReplicationStatus.YYYY_MM_DD_HH_MM_SS.out

```
admin:file view activelog er/trace/dbl/sdi/ReplicationStatus.2015_01_21_12_28_48.out

Wed Jan 21 12:28:48 2015 main()  DEBUG:  -->
Wed Jan 21 12:28:48 2015 main()  DEBUG:  Replication cluster summary:
SERVER          ID STATE      STATUS      QUEUE  CONNECTION CHANGED
-----
g_cer10_cer10_0_2_10000_11    2 Active    Local      0
g_cersub_cer10_0_2_10000_11   3 Active    Connected  0 Jan  8 15:40:17
Wed Jan 21 12:28:48 2015 main()  DEBUG:  <--

end of the file reached
options: q=quit, n=next, p=prev, b=begin, e=end (lines 1 - 7 of 7) :
admin:
```

如果看到以下輸出，而不是如上所述的「已連線」(Connected)，則會發現複製設定不正確。

```
SERVER          ID STATE      STATUS      QUEUE  CONNECTION CHANGED
-----
g_cer10_cer10_0_2_10000_11    2 Active    Local      0
g_cersub_cer10_0_2_10000_11   3 Active    Connecting 165527
```

```
SERVER          ID STATE      STATUS      QUEUE  CONNECTION CHANGED
-----
g_cer10_cer10_0_2_10000_11    2 Active    Local      0
```

g_cersub_cer10_0_2_10000_11 3 Active **Disconnect** 0

如有必要，重複該過程

如果複製仍不成功，您可能需要重複此過程多達兩次。如果在執行此過程3次後複製失敗，請刪除並重新安裝訂閱伺服器。