# Configure Default Domain Name and Multi PG Supervisor in Cisco CCE 12.X

### **Contents**

Introduction

**Prerequisites** 

Requirements

**Components Used** 

**Background Information** 

**Configure** 

Step 1. Set global domain

Step 2. Create a supervisor

Step 3. Create a supervisor for the same person on another peripheral.

Verify

**Troubleshoot** 

#### Introduction

This document describes the steps needed to configure default domain name in Cisco Unified Contact Center Enterprise (CCE). In addition, this documents explains how to create and enable supervisor for multiple Cisco Unified Communication Manager (CUCM) peripheral gateway (PG) in CCE environment in a non-signle sign-on (SSO) solution.

Contributed by Anuj Bhatia, Cisco TAC Engineer.

## **Prerequisites**

#### Requirements

Cisco recommends that you have knowledge of these topics:

- Cisco Unified Contact Center Enterprise (CCE)
- Microsoft Active Directory (AD)

## **Components Used**

The information used in the document is based on UCCE solution 12.0(1) version.

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live, ensure that you understand the potential impact of any step.

# **Background Information**

UCCE 12.X solution in a non-SSO environment allows supervisors to log in with user name, there is no restriction on UserPrincipalName (UPN) or samAccountName (SAM) account format. The solution acheives this setup by the addition of a default domain name option where you can choose the domain, and when supervisor logs in with username, CCE attaches the global domain name to the user name as needed.


This enhancement is also helpfull for scenarios where supervisor sign in for multiple PGs (tradionally they would require to sign in with UPN formatted usernames).

Required steps to configure the same is highlighted in the configure section


## Configure

#### Step 1. Set global domain

- 1. Log in to the administrator server (AW) with a CCE setup rights user.
- 2. Launch the **System Information** tool from **Configuration manager > Miscellaneous Tools** section.
- 3. Select the domain from the **Default domain name** field and save it.




4. To confirm the change run the stated query against the AW database and examine the User\_Group table for the domain name and where it is stored.



#### Step 2. Create a supervisor

- 1. Launch the Agent Explorer from Configuration manager tool and create a new agent.
- 2. Promote the agent to supervisor level. Check the Supervisor checkbox. At this point, the tool validates the presence of agent\_one in active directory.




If there are no errors the user configuration with username is saved.


3. At this stage agent\_one can log in into Finesse , CUIC and CCEAdmin page just with the username.

## Step 3. Create a supervisor for the same person on another peripheral.


- 1. Open the agent explorer via configuration manager tool and change the peripheral pulldown to a different CUCM PG server, as an example in this case cucm\_pg2 peripheral is used.
- 2. Select Add Agent and then do **Select Person**.
- 3. Choose the same agent agent\_one from the list and press OK.



4. Select the supervisor checkbox and save the record.



- 5. There are now 2 supervisors connected to the same person record.
- 6. Check the Agent and Person tables to confirm this assocation.



Supervisor with the same credentials are able to log in to finesse server of there respective peripheral's and monitor the desired teams.

# Verify

There is currently no verification procedure available for this configuration.

## **Troubleshoot**

There is currently no specific troubleshooting information available for this configuration.