



## LISP Show Commands

---

- [show adjacency \(IP Routing LISP\), on page 3](#)
- [show ip lisp, on page 4](#)
- [show ip lisp database, on page 8](#)
- [show lisp instance-id ipv4 database, on page 10](#)
- [show ip lisp forwarding, on page 11](#)
- [show ip lisp instance-id ipv4 forwarding, on page 14](#)
- [show ip lisp instance-id, on page 16](#)
- [show lisp instance-id ipv4 alt, on page 17](#)
- [show ip lisp locator-table, on page 18](#)
- [show ip lisp map-cache, on page 20](#)
- [show lisp instance-id ipv4 map-cache, on page 23](#)
- [show ip lisp route-import database, on page 25](#)
- [show lisp instance-id ipv4 route-import database, on page 27](#)
- [show ip lisp route-import map-cache, on page 29](#)
- [show lisp instance-id ipv4 route-import map-cache, on page 31](#)
- [show ip lisp statistics, on page 33](#)
- [show lisp ipv4 statistics, on page 35](#)
- [show ipv6 lisp, on page 37](#)
- [show ipv6 lisp database, on page 41](#)
- [show lisp instance-id ipv6 database, on page 43](#)
- [show ipv6 lisp forwarding, on page 44](#)
- [show lisp instance-id ipv6 forwarding, on page 47](#)
- [show ipv6 lisp instance-id, on page 50](#)
- [show lisp instance-id ipv6 alt, on page 51](#)
- [show ipv6 lisp locator-table, on page 52](#)
- [show ipv6 lisp map-cache, on page 54](#)
- [show lisp instance-id ipv6 map-cache, on page 56](#)
- [show ipv6 lisp route-import database, on page 58](#)
- [show lisp instance-id ipv6 route-import database, on page 60](#)
- [show ipv6 lisp route-import map-cache, on page 62](#)
- [show lisp instance-id ipv6 route-import map-cache, on page 64](#)
- [show ipv6 lisp statistics, on page 66](#)
- [show lisp ipv6 statistics, on page 68](#)

- [show lisp](#), on page 69
- [show lisp ddt](#), on page 70
- [show lisp decapsulation filter](#), on page 72
- [show lisp instance-id](#), on page 74
- [show lisp locator-table](#), on page 75
- [show lisp site](#), on page 77
- [show lisp site rloc members](#), on page 79
- [show lisp session](#), on page 81

# show adjacency (IP Routing LISP)

To display information about adjacency table, use the show adjacency command in user EXEC or privileged EXEC mode.

**show adjacency** {**connid-mgr** | **LISP***interface-number ip-address***connectionid xkeys ip-address**[**vrf vrf-name**]**dport port-number**} [{**detail** | **summary**}]

Syntax Description		
<b>connid-mgr</b>		Displays information about connection IDs that are currently being managed by infrastructure.
<b>LISP</b> <i>interface-number ip-address</i>		Interface and IP address, optionally, VRF, of LISP for which connection ID is displayed.
<b>connectionid xkeys</b> <i>ip-address</i> [ <b>vrf vrf-name</b> ]		Displays information about connection ID and extended keys.
<b>dport</b> <i>port-number</i>		Displays information about destination port.
<b>detail</b>		Displays detailed adjacency information.
<b>summary</b>		Displays a summary of adjacency information.

**Command Modes** Privileged EXEC (#)

Command History	Release	Modification
	Cisco IOS XE Fuji 16.9.1	This command was introduced.

**Usage Guidelines** You can view adjacencies with the assigned managed connection id, or their extended keys using this command.

## Examples

The following is a sample output from the **show adjacency** command displaying the connection ID.

```
Device# show adjacency LISP0 172.16.1.21 connectionid 2130706434 detail
Protocol Interface Address
IP LISP0 172.16.1.21(6)
connectionid 2130706434
src 172.16.0.2 vrf 0
dst port 1027
```

The following is a sample output from the show adjacency command displaying the extended keys.

```
Device# show adjacency LISP0 172.16.1.21 connectionid xkeys 172.16.0.2 dport 1027 detail
Protocol Interface Address
IP LISP0 172.16.1.21(6)
connectionid 2130706434
src 172.16.0.2 vrf 0
dst port 1027
```

# show ip lisp



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp service ipv4/ipv6** or **show lisp instance-id [0-16777200] ipv4/ipv6**.

To display the IPv4 Locator ID Separation Protocol (LISP) configuration status, use the **show ip lisp** command in privileged EXEC mode.

```
show ip lisp [{router-lisp-id}]
```

## Syntax Description

<i>router-lisp-id</i>	(Optional) Router LISP instantiation ID. Valid values are 0 to 15.
-----------------------	--

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
15.1(1)XB	This command was introduced.
15.1(1)XB1	This command was modified.
Cisco IOS XE Release 2.5.1XA	This command was integrated into Cisco IOS XE Release 2.5.1XA.
15.1(1)XB2	This command was modified.
Cisco IOS XE Release 2.5.1XB	This command was modified.
15.1(4)M	This command was integrated into Cisco IOS Release 15.1(4)M and modified to include the <b>locator-table</b> keyword.
Cisco IOS XE Release 3.3S	This command was integrated into Cisco IOS XE Release 3.3S and modified to include the <b>locator-table</b> keyword.

## Usage Guidelines

When used without the optional router LISP ID value, the **show ip lisp** command displays the IPv4 LISP configuration status for the local device for the default router LISP instantiation. When the *router-lisp-id* argument is used, the command displays the IPv4 LISP configuration status for the specified router LISP instantiation.

## Examples

The following sample output from the **show ip lisp** command displays information about the current IPv4 LISP configuration status. The output varies, depending on the LISP features configured.

```
Router# show ip lisp

Instance ID:                0
  Ingress Tunnel Router (ITR):  enabled
  Egress Tunnel Router (ETR):   enabled
```

```

Proxy-ITR Router (PITR):      disabled
Proxy-ETR Router (PETR):     disabled
Map Server (MS):             disabled
Map Resolver (MR):           disabled
Map-Request source:          10.0.2.1
ITR Map-Resolver:            10.0.100.2
ETR Map-Server(s):           10.0.100.2 (00:00:37)
ITR Solicit Map Request (SMR): accept and process
    Max SMRs per map-cache entry: 8 more specifics
    Multiple SMR suppression time: 60 secs
ETR accept mapping data:     disabled, verify disabled
ETR map-cache TTL:           1d00h
Locator Status Algorithms:
    RLOC-probe algorithm:     disabled
Static mappings configured:   0
Map-cache size/limit:         1/1000
Map-cache activity check period: 60 secs
Map-database size:           1
Persistent map-cache:         interval 00:10:00
    Earliest next store:      00:05:28
    Location: flash:LISP-MapCache-IPv4-00000000-00030
Router#

```

The table below describes the significant fields shown in the display.

**Table 1: show ip lisp Field Descriptions**

Field	Description
Ingress Tunnel Router (ITR)	Indicates whether the router is configured as an ITR. See the <b>ipv4 itr</b> command.
Egress Tunnel Router (ETR)	Indicates whether the router is configured as an ETR. See the <b>ipv4 etr</b> command.
Proxy-ITR (PITR)	Indicates whether the router is configured as a PITR. See the <b>ipv4 proxy-itr</b> command.
Proxy-ETR (PETR)	Indicates whether the router is configured as a PETR. See the <b>ipv4 proxy-etr</b> command.
Map Server (MS)	Indicates whether the router is configured as a map server. See the <b>ipv4 map-server</b> command.
Map Resolver (MR)	Indicates whether the router is configured as a map resolver. See the <b>ipv4 map-resolver</b> command. .
Map-Request source	Identifies the IPv4 address used as the source in Map Request messages.
ITR Map-Resolver	Identifies the configured ITR map resolver. See the <b>ipv4map-resolver</b> command.
ETR Map-Server(s)	Identifies the configured ETR map servers. See the <b>ipv4 map-server</b> command.
ITR Solicit Map Request (SMR)	Indicates whether SMRs are accepted and processed. See the <b>ipv4 solicit-map-request</b> command.

Field	Description
ETR accept mapping data	Indicates whether the ETR is configured to cache the mapping data contained in a map request. See the <b>ipv4 etr accept-map-request-mapping</b> command.
ETR map-cache TTL	Identifies the current ETR map cache time-to-live (TTL) value. See the <b>ipv4 etr map-cache-ttl</b> command.
Locator Status Algorithms	Indicates whether the locator reachability algorithm routing locator (RLOC) probing is enabled. See the <b>loc-reach-algorithm</b> command.
Static mappings configured	Indicates the number of static cache-map entries configured. See the <b>map-cache</b> command.
Map-cache size/limit	Indicates the number of entries currently in the map cache and indicates the limit value. See the <b>ipv4 map-cache-limit</b> command.
Map-cache activity check period	Indicates how often the control plane checks the map cache for outbound usage activity.
Map-database size	Indicates the number of entries currently in the map database. See the <b>database-mapping</b> .
Persistent map-cache	Indicates the persistent map-cache timer interval, next use, and storage location. See the <b>ipv4 map-cache-persistent</b> command.
ITR use proxy ETR RLOC configuration	Indicates that the router uses PETR services, and lists the PETR locator. See the <b>ipv4 use-petr</b> command.

The following sample output from the **show ip lisp** command displays information about the current IPv4 LISP configuration status when a LISP instantiation has been created using the **router lisp id** command and the **locator-table** command. Below, the results shown are based on router lisp 6 and locator-table vrf Cust-1. (Other output varies depending on the LISP features configured.)

```
Router# show ip lisp 6

Information applicable to all EID instances:
Router-lisp ID:          6
Locator table:          vrf Cust-1
Ingress Tunnel Router (ITR): enabled
Egress Tunnel Router (ETR): enabled
---<more>---
```

#### Related Commands

Command	Description
<b>database-mapping</b>	Configure an IPv4 or IPv6 EID-to-RLOC mapping relationship and its associated traffic policy for LISP.
<b>eid-table</b>	Configures a LISP instance ID for association with a VRF table or default table through which the EID address space is reachable.
<b>ip lisp source-locator</b>	Configures a source locator to be used for an IPv4 LISP-encapsulated packets.

Command	Description
<b>ipv4 etr</b>	Configures the router to act as an IPv4 LISP ETR.
<b>ipv4 etr accept-map-request-mapping</b>	Configures an ETR to cache IPv4 mapping data contained in a map-request message.
<b>ipv4 etr map-cache-ttl</b>	Configures the TTL value inserted into LISP IPv4 map-reply messages.
<b>ipv4 etr map-server</b>	Configures the IPv4 or IPv6 locator address of the LISP map server to be used by the ETR when registering for IPv4 EIDs.
<b>ipv4 itr</b>	Configures the router to act as an IPv4 LISP ITR.
<b>ipv4 itr map-resolver</b>	Configures the IPv4 locator address of the LISP map resolver to be used by the ITR when sending map requests for IPv4 EID-to-RLOC mapping resolution.
<b>ipv4 map-cache-limit</b>	Configures the maximum number of IPv4 LISP map-cache entries allowed to be stored by the router.
<b>ipv4 map-cache-persistent</b>	Configures how often, in minutes, that an ITR should save its dynamically learned map-cache entries to a file in flash.
<b>ipv4 map-resolver</b>	Configures a router to act as an IPv4 LISP map resolver.
<b>ipv4 map-server</b>	Configures a router to act as an IPv4 LISP map server.
<b>ipv4 solicit-map-request ignore</b>	Configures an ITR to ignore an IPv4 Map Request message that has the solicit-map-request (SMR) bit set.
<b>ipv4 proxy-etr</b>	Configures the router to act as an IPv4 LISP PETR.
<b>ipv4 proxy-itr</b>	Configures the router to act as an IPv4 LISP PITR.
<b>ipv4 use-petr</b>	Configures a router to use a LISP PETR.
<b>locator-table</b>	Configure the association of a VRF table through which the routing locator address space is reachable to a router LISP instantiation.
<b>map-cache</b>	Configures a static IPv4 or IPv6 EID-to-RLOC mapping relationship and its associated traffic policy, or statically configures the packet handling behavior associated with a specified destination IPv4 or IPv6 EID prefix.
<b>router lisp</b>	Enters LISP configuration mode and configures LISP commands on a router.
<b>show ip lisp locator-table</b>	Displays the IPv4 LISP ETR configured local IPv4 EID prefixes and associated locator sets.

# show ip lisp database



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp instance-id [0-16777200] ipv4 database**.

To display Locator/ID Separation Protocol (LISP) Egress Tunnel Router (ETR) configured local IPv4 EID prefixes and associated locator sets, use the **show ip lisp database** command in privileged EXEC mode.

**show ip lisp database** [*EID-prefix*]

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
15.1(1)XB	This command was introduced.
Cisco IOS XE Release 2.5.1XA	This command was integrated into Cisco IOS XE Release 2.5.1XA.
Cisco IOS XE Release 3.3.0S	This command was integrated into Cisco IOS XE Release 3.3.0S.
15.1(4)M	This command was integrated into Cisco IOS Release 15.1(4)M.

## Usage Guidelines

This command is used on LISP ETR devices to display the configured local IPv4 EID prefixes and associated locator sets.

## Examples

The following sample output from the **show ip lisp database** command displays the configured IPv4 EID-prefix blocks and associated locator sets. The output of this command shows the configured IPv4 endpoint identifier-to-routing locator (EID-to-RLOC) database mappings.

```
Router# show running-config
.
.
.
!
database-mapping 172.16.21.0/24 192.168.156.222 priority 1 weight 100

Router# show ip lisp database

LISP ETR IPv4 Mapping Database

EID-prefix: 172.16.21.0/28
  192.168.156.222, priority: 1, weight: 100, state: up, local
```



**Related Commands**

Command	Description
<b>database-mapping</b>	Configures an IPv6 EID-to-RLOC mapping relationship and its associated traffic policy.

## show lisp instance-id ipv4 database

To display the Locator ID Separation Protocol (LISP) Egress Tunnel Router (ETR) configured local IPv4 EID prefixes and associated locator sets, use the **show lisp instance-id [0-16777200] ipv4 database** command in the privileged EXEC mode.

**show lisp instance-id [0-16777200] ipv4 database**

### Command Modes

Privileged EXEC (#)

### Command History

Release	Modification
Cisco IOS XE Dublin 17.11.1a	This command was introduced.

### Usage Guidelines

This command is used on LISP ETR devices to display the configured local IPv4 EID prefixes and associated locator sets.

### Examples

The following sample output from the **show ip lisp instance-id [0-16777200] ipv4 database** command displays the configured IPv4 EID-prefix blocks and associated locator sets. The output of this command shows the configured IPv4 endpoint identifier-to-routing locator (EID-to-RLOC) database mappings.

```
Router# show running-config
.
.
.
!
database-mapping 172.16.21.0/24 192.168.156.222 priority 1 weight 100

Router# show lisp instance-id 0 ipv4 database

LISP ETR IPv4 Mapping Database

EID-prefix: 172.16.21.0/28
  192.168.156.222, priority: 1, weight: 100, state: up, local
```

### Related Commands

Command	Description
<b>database-mapping</b>	Configures an IPv6 EID-to-RLOC mapping relationship and its associated traffic policy.

# show ip lisp forwarding



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp instance-id [0-16777200] ipv4 forwarding**.

To display Locator/ID Separation Protocol (LISP) IPv4 EID-prefix information, use the **show ip lisp forwarding** command in privileged EXEC mode.

**show ip lisp forwarding** {**eid** {**local** | **remote** [*eid-prefix* | **detail**]} | **state**}

## Syntax Description

<b>eid</b>	Displays information related to EID prefixes (local or remote)
<b>local</b>	Displays locally configured EID prefixes.
<b>remote</b>	Displays forwarding action and locator status bits for dynamically learned EID-prefix blocks, and the number of packets and total bytes encapsulated
<i>eid-prefix</i>	(Optional) The specific remote EID prefix for which associated detailed information is displayed.
<b>detail</b>	(Optional) Displays detailed information associated with each remote EID prefix.
<b>state</b>	Displays information about the LISP module forwarding state

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
15.1(1)XB	This command was introduced.
15.1(1)XB1	This command was modified.
Cisco IOS XE Release 2.5.1XA	This command was integrated into Cisco IOS XE Release 2.5.1XA
Cisco IOS XE Release 3.3.0S	This command was integrated into Cisco IOS XE Release 3.3.0S.
15.1(4)M	This command was integrated into Cisco IOS Release 15.1(4)M.

## Usage Guidelines

This command is used to display information for either local or remote IPv4 EID prefixes. Local IPv4 EID prefixes are those for which the router is authoritative and added via the **database-mapping** command. Remote IPv4 EID prefixes are for remote sites and learned dynamically through map-reply information or via map-request messages when the **ipv4 etr accept-map-request-mapping** command is configured.

## Examples

The following sample output from the **show ip lisp forwarding eid local** command displays local IPv4 EID-prefix information.

```
Router# show ip lisp forwarding eid local
```

```
Prefix
192.168.1.0/24
192.168.100.0/24
```

The following sample output from the **show ip lisp forwarding eid remote** command displays summary remote IPv4 EID prefix information when the keyword **detail** is not used. The display shows EID prefix, associated locator status bits, and total encapsulated packets and bytes for each remote IPv4 EID prefix.

```
Router# show ip lisp forwarding eid remote
```

```
Prefix          Fwd action  Locator status bits
0.0.0.0/0      signal     0x00000000
  packets/bytes 1/86
192.168.2.0/24 encap      0x00000003
  packets/bytes 4/344
192.168.3.0/24 encap      0x00000003
  packets/bytes 5/430
```

The following sample output from the **show ip lisp forwarding eid remote detail** command displays detailed remote IPv4 EID-prefix information by adding the **detail** keyword. The display shows EID prefix, associated locator status bits, and total encapsulated packets and bytes for each remote IPv4 EID-prefix.

```
Router# show ip lisp forwarding eid remote detail
```

```
Prefix          Fwd action  Locator status bits
0.0.0.0/0      signal     0x00000000
  packets/bytes 1/86
  path list 060A4690, flags 0x49, 3 locks, per-destination
  ifnums:
    LISP0(14)
  1 path
    path 060A4DF0, path list 060A4690, share 1/1, type attached prefix, for IPv4
    attached to LISP0, adjacency glean for LISP0
  1 output chain
    chain[0]: glean for LISP0
192.168.2.0/24  encap      0x00000003
  packets/bytes 19/1634
  path list 06BFA2B8, flags 0x49, 5 locks, per-destination
  ifnums:
    LISP0(14): 10.0.0.6
  1 path
    path 06E8C8C0, path list 06BFA2B8, share 100/100, type attached nexthop, for IPv4
    nexthop 10.0.0.6 LISP0, adjacency IP midchain out of LISP0, addr 10.0.0.6 073747B8
  1 output chain
Prefix          Fwd action  Locator status bits
  chain[0]: IP midchain out of LISP0, addr 10.0.0.6 073747B8 IP adj out of Ethernet0/0,
  addr 10.0.0.2 0620D8A8
192.168.3.0/24  encap      0x00000003
```

The following sample output from the **show ip lisp forwarding state** command displays detailed information about the state of the LISP process forwarding state. ( IPv4 and IPv6 information is presented).

```
Router# show ip lisp forwarding state
```

```
LISP forwarding state for EID table IPv4:Default
```

```

EID VRF                               Default (0x0)
  IPv4
    Configured roles                    ITR|ETR
    Active roles                        ITR|ETR
    EID table                           IPv4:Default
    ALT table                           <null>
    Locator status bits                 0x00000001
  IPv6
    Configured roles                    ITR|ETR
    Active roles                        ITR|ETR
    EID table                           IPv6:Default
    ALT table                           <null>
    Locator status bits                 0x00000001
RLOC transport VRF                    Default (0x0)
  IPv4 RLOC table                      IPv4:Default
  IPv6 RLOC table                      IPv6:Default
LISP virtual interface                LISP0

```

**Related Commands**

Command	Description
<b>database-mapping</b>	Configures an IPv6 EID-to-RLOC mapping relationship and its associated traffic policy.
<b>ipv4 etr accept-map- request-mapping</b>	Configures an ETR to cache IPv4 mapping data contained in a map-request message.
<b>show ip lisp map-cache</b>	Displays the current dynamic and static IPv4 EID-to-RLOC map-cache entries.

# show ip lisp instance-id ipv4 forwarding

To display Locator/ID Separation Protocol (LISP) IPv4 EID-prefix information, use the **show lisp instance-id [0-16777200] ipv4 forwarding** command in privileged EXEC mode.

**show lisp instance-id [0-16777200] ipv4 forwarding**

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
Cisco IOS XE Dublin 17.11.1a	This command was introduced.

## Usage Guidelines

This command is used to display information for either local or remote IPv4 EID prefixes. Local IPv4 EID prefixes are those for which the router is authoritative and added via the **database-mapping** command. Remote IPv4 EID prefixes are for remote sites and learned dynamically through map-reply information or via map-request messages when the **ipv4 etr accept-map-request-mapping** command is configured.

## Examples

The following sample output from the **show lisp forwarding instance-id [0-16777200] ipv4 forwarding eid local** command displays local IPv4 EID-prefix information.

```
Router# show lisp instance-id 0 ipv4 forwarding eid local

Prefix
192.168.1.0/24
192.168.100.0/24
```

The following sample output from the **show lisp instance-id [0-16777200] ipv4 forwarding eid remote** command displays summary remote IPv4 EID prefix information when the keyword **detail** is not used. The display shows EID prefix, associated locator status bits, and total encapsulated packets and bytes for each remote IPv4 EID prefix.

```
Router# show lisp instance-id 0 ipv4 forwarding eid remote

Prefix          Fwd action  Locator status bits
0.0.0.0/0       signal      0x00000000
  packets/bytes  1/86
192.168.2.0/24  encap       0x00000003
  packets/bytes  4/344
192.168.3.0/24  encap       0x00000003
  packets/bytes  5/430
```

The following sample output from the **show lisp instance-id [0-16777200] ipv4 forwarding eid remote detail** command displays detailed remote IPv4 EID-prefix information by adding the **detail** keyword. The display shows EID prefix, associated locator status bits, and total encapsulated packets and bytes for each remote IPv4 EID-prefix.

```
Router# show lisp instance-id 0 ipv4 forwarding eid remote detail

Prefix          Fwd action  Locator status bits
0.0.0.0/0       signal      0x00000000
  packets/bytes  1/86
```

```

path list 060A4690, flags 0x49, 3 locks, per-destination
ifnums:
  LISP0(14)
  1 path
    path 060A4DF0, path list 060A4690, share 1/1, type attached prefix, for IPv4
    attached to LISP0, adjacency glean for LISP0
  1 output chain
chain[0]: glean for LISP0
192.168.2.0/24          encap          0x00000003
packets/bytes         19/1634
path list 06BFA2B8, flags 0x49, 5 locks, per-destination
ifnums:
  LISP0(14): 10.0.0.6
  1 path
    path 06E8C8C0, path list 06BFA2B8, share 100/100, type attached nexthop, for IPv4
    nexthop 10.0.0.6 LISP0, adjacency IP midchain out of LISP0, addr 10.0.0.6 073747B8
  1 output chain
Prefix                Fwd action  Locator status bits
chain[0]: IP midchain out of LISP0, addr 10.0.0.6 073747B8 IP adj out of Ethernet0/0,
addr 10.0.0.2 0620D8A8
192.168.3.0/24          encap          0x00000003

```

The following sample output from the **show lisp instance-id [0-16777200] ipv4 forwarding state** command displays detailed information about the state of the LISP process forwarding state. ( IPv4 and IPv6 information is presented).

```
Router# show lisp instance-id 0 ipv4 forwarding state
```

```

LISP forwarding state for EID table IPv4:Default
EID VRF                Default (0x0)
  IPv4
    Configured roles    ITR|ETR
    Active roles        ITR|ETR
    EID table            IPv4:Default
    ALT table            <null>
    Locator status bits 0x00000001
  IPv6
    Configured roles    ITR|ETR
    Active roles        ITR|ETR
    EID table            IPv6:Default
    ALT table            <null>
    Locator status bits 0x00000001
RLOC transport VRF     Default (0x0)
  IPv4 RLOC table      IPv4:Default
  IPv6 RLOC table      IPv6:Default
LISP virtual interface LISP0

```

#### Related Commands

Command	Description
<b>database-mapping</b>	Configures an IPv6 EID-to-RLOC mapping relationship and its associated traffic policy.
<b>ipv4 etr accept-map- request-mapping</b>	Configures an ETR to cache IPv4 mapping data contained in a map-request message.
<b>show ip lisp map-cache</b>	Displays the current dynamic and static IPv4 EID-to-RLOC map-cache entries.

# show ip lisp instance-id



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp instance-id [0-16777200] ipv4 alt**.

To display the negative prefix hole in the LISP ALT for an EID within a specified instance-id, use the **show ip lisp instance-id** command in privileged EXEC mode.

**show ip lisp instance-id iid alt negative-prefix EID-prefix**

## Syntax Description

<i>iid</i>	EID instance-id.
<i>EID-prefix</i>	IPv4 EID address covered by negative ALT prefix.

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
15.1(1)XB3	This command was introduced.
2.5.1XC	This command was integrated into Cisco IOS XE Release 2.5.1XC.

## Usage Guidelines

This command is only used on LISP Map-Server (MS) devices to display the negative prefix hole in the LISP ALT for an EID within a specified instance-id.

## Examples

The following sample output from the show ip lisp instance-id command for the instance-id 123 and EID 172.16.0.1.

```
Router# show ip lisp instance-id 123 alt negative-prefix 172.16.0.1
Negative mapping system prefix 128.0.0.0/2
Router#
```

## Related Commands

Command	Description
<b>eid-prefix (LISP site)</b>	Configures the EID-prefix associated with a LISP site on a Map-Server as part of the LISP Site configuration process.



# show lisp instance-id ipv4 alt

To display the negative prefix hole in the LISP ALT for an EID within a specified instance-id, use the **show lisp instance-id [0-16777200] ipv4 alt** command in privileged EXEC mode.

```
show lisp instance-id [0-16777200] ipv4 alt
```

**Command Modes** Privileged EXEC (#)

Command History	Release	Modification
	Cisco IOS XE Dublin 17.11.1a	This command was introduced.

**Usage Guidelines** This command is only used on LISP Map-Server (MS) devices to display the negative prefix hole in the LISP ALT for an EID within a specified instance-id.

**Examples** The following sample output from the **show lisp instance-id ipv4 alt** command for the instance-id 123 and EID 172.16.0.1.

```
Router# show lisp instance-id 123 ipv4 alt negative-prefix 172.16.0.1
Negative mapping system prefix 128.0.0.0/2
Router#
```

Related Commands	Command	Description
	<b>eid-prefix (LISP site)</b>	Configures the EID-prefix associated with a LISP site on a Map-Server as part of the LISP Site configuration process.

# show ip lisp locator-table



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp locator table**.

To display Locator/ID Separation Protocol (LISP) IPv4 configurations associated with a specific locator table, use the **show ip lisp locator-table** command in privileged EXEC mode.

**show ip lisp locator-table** {**default** | **vrf** *vrf-name*}

## Syntax Description

<b>default</b>	Displays IPv4 LISP information and configuration status related to the default table.
<b>vrf</b> <i>vrf-name</i>	Displays IPv4 LISP information and configuration status related to the specified virtual routing and forwarding (VRF) table.

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
15.1(1)XB6	This command was introduced.
15.1(4)M	This command was integrated into Cisco IOS Release 15.1(4)M.
Cisco IOS XE Release 3.3S	This command was integrated into Cisco IOS XE Release 3.3S.

## Usage Guidelines

The **locator-table** command creates an association between a LISP instantiation and a virtual routing and forwarding (VRF) table through which the routing locator address space is reachable. The **show ip lisp locator-table** command displays the IPv4 LISP configuration status for a specific locator table. A locator table can be the default, meaning the global routing table, or id can be a specific VRF.

## Examples

The following shows sample output from the **show ip lisp locator-table** command for the vrf Cust-1:

```
Router# show ip lisp locator-table Cust-1

Information applicable to all EID instances:
Router-lisp ID:                1
Locator table:                 vrf Cust-1
Ingress Tunnel Router (ITR):   disabled
Egress Tunnel Router (ETR):    disabled
Proxy-ITR Router (PITR):      enabled RLOCs: 10.100.8.2
Proxy-ETR Router (PETR):      enabled
Map Server (MS):              disabled
Map Resolver (MR):            disabled
Delegated Database Tree (DDT): disabled
ITR Map-Resolver(s):          10.100.1.2
ITR Solicit Map Request (SMR): accept and process
  Max SMRs per map-cache entry: 8 more specifics
  Multiple SMR suppression time: 20 secs
```

```
ETR accept mapping data:      disabled, verify disabled
ETR map-cache TTL:           1d00h
Locator Status Algorithms:
  RLOC-probe algorithm:      disabled
  LSB reports:               process
Map-cache limit:             1000
Map-cache activity check period: 60 secs
Persistent map-cache:       disabled
Router#
```

**Related Commands**

Command	Description
<b>locator-table</b>	Configures the association of a VRF table through which the routing locator address space is reachable to a router LISP instantiation.

# show ip lisp map-cache



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp instance-id [0-16777200] ipv4 map-cache**.

To display the current dynamic and static IPv4 endpoint identifier-to-routing locator (EID-to-RLOC) map-cache entries, use the **show ip lisp map-cache** command in privileged EXEC mode.

**show ip lisp map-cache** [*destination-EID* | *destination-EID-prefix/prefix-length* | **eid-table** {**default** | **vrfname** | **detail**}]

## Syntax Description

<i>destination-EID</i>	(Optional) Destination EID for which to display mapping.
<i>destination-EID-prefix/prefix-length</i>	(Optional) Destination EID prefix for which to display mapping.
<b>eid-table</b>	(Optional) Specifies an EID table for which to display mapping.
<b>default</b>	(Optional) Displays detailed information for the default virtual routing and forwarding (VRF).
<b>vrf name</b>	(Optional) Displays detailed information for the identified VRF.
<b>detail</b>	(Optional) Displays detailed EID-to-RLOC cache mapping information

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
15.1(1)XB	This command was introduced.
15.1(1)XB1	This command was modified.
Cisco IOS XE2.5.1XA	This command was integrated into Cisco IOS XE Release 2.5.1XA
Cisco IOS XE Release 3.3.0S	This command was integrated into Cisco IOS XE Release 3.3.0S.
15.1(4)M	This command was integrated into Cisco IOS Release 15.1(4)M.

## Usage Guidelines

This command is used to display the current dynamic and static IPv4 EID-to-RLOC map-cache entries. When no IPv4 EID or IPv4 EID prefix is specified, summary information is listed for all current dynamic and static IPv4 EID-to-RLOC map-cache entries. When an IPv4 EID or IPv4 EID prefix is included, information is

listed for the longest-match lookup in the cache. When the **detail** option is used, detailed (rather than summary) information related to all current dynamic and static IPv4 EID-to-RLOC map-cache entries is displayed.

## Examples

The following sample output from the **show ip lisp map-cache** command (without the use of an IPv4 EID or IPv4 EID prefix) displays a summary list of current dynamic and static IPv4 EID-to-RLOC map-cache entries. The display shows IPv4 EID prefix and associated information.

```
Router# show ip lisp map-cache

LISP IPv4 Mapping Cache, 2 entries
0.0.0.0/0, uptime: 00:00:17, expires: never, via static
  Negative cache entry, action: send-map-request
192.168.2.0/24, uptime: 00:00:02, expires: 23:59:54, via map-reply, complete
  Locator  Uptime   State     Pri/Wgt
  10.0.0.6  00:00:02  up       1/100
  10.1.0.6  00:00:02  admin-down 255/0
```

The following sample output from the **show ip lisp map-cache detail** command displays a detailed list of current dynamic and static IPv4 EID-to-RLOC map-cache entries.

```
Router# show ip lisp map-cache detail

LISP IPv4 Mapping Cache, 2 entries

0.0.0.0/0, uptime: 00:00:41, expires: never, via static
  State: send-map-request, last modified: 00:00:41, map-source: local
  Idle, Packets out: 0
  Negative cache entry, action: send-map-request
192.168.2.0/24, uptime: 00:00:26, expires: 23:59:31, via map-reply, complete
  State: complete, last modified: 00:00:26, map-source: 10.0.0.6
  Active, Packets out: 0
  Locator  Uptime   State     Pri/Wgt
  10.0.0.6  00:00:26  up       1/100
    Last up-down state change:      never, state change count: 0
    Last priority / weight change:  never/never
    RLOC-probing loc-status algorithm:
      Last RLOC-probe sent:        never
  10.1.0.6  00:00:26  admin-down 255/0
    Last up-down state change:      never, state change count: 0
    Last priority / weight change:  never/never
    RLOC-probing loc-status algorithm:
      Last RLOC-probe sent:        never
```

The following sample output from the **show ip lisp map-cache** command with a specific IPv4 EID prefix displays detailed information associated with that IPv4 EID-prefix entry.

```
Router# show ip lisp map-cache 192.168.2.0/24

LISP IPv4 Mapping Cache, 2 entries

192.168.2.0/24, uptime: 00:01:01, expires: 23:58:56, via map-reply, complete
  State: complete, last modified: 00:01:01, map-source: 10.0.0.6
  Active, Packets out: 0
  Locator  Uptime   State     Pri/Wgt
  10.0.0.6  00:01:01  up       1/100
    Last up-down state change:      never, state change count: 0
    Last priority / weight change:  never/never
    RLOC-probing loc-status algorithm:
      Last RLOC-probe sent:        never
  10.1.0.6  00:01:01  admin-down 255/0
```

**show ip lisp map-cache**

```
Last up-down state change:      never, state change count: 0
Last priority / weight change:  never/never
RLOC-probing loc-status algorithm:
  Last RLOC-probe sent:         never
```

**Related Commands**

<b>Command</b>	<b>Description</b>
<b>show ip lisp forwarding</b>	Displays LISP local or remote IPv4 EID-prefix information.

## show lisp instance-id ipv4 map-cache

To display the current dynamic and static IPv4 endpoint identifier-to-routing locator (EID-to-RLOC) map-cache entries, use the **show lisp instance-id ipv4 map-cache** command in privileged EXEC mode.

```
show lisp instance-id ipv4 map-cache [{ destination-EID | destination-EID-prefix / prefix-length
| eid-table { default | vrf name | detail } }]
```

Syntax Description		
<i>destination-EID</i>	(Optional) Destination EID for which to display mapping.	
<i>destination-EID-prefix/prefix-length</i>	(Optional) Destination EID prefix for which to display mapping.	
<b>eid-table</b>	(Optional) Specifies an EID table for which to display mapping.	
<b>default</b>	(Optional) Displays detailed information for the default virtual routing and forwarding (VRF).	
<b>vrf name</b>	(Optional) Displays detailed information for the identified VRF.	
<b>detail</b>	(Optional) Displays detailed EID-to-RLOC cache mapping information	

**Command Modes** Privileged EXEC (#)

Command History	Release	Modification
	Cisco IOS XE Dublin 17.11.1a	This command was introduced.

**Usage Guidelines** This command is used to display the current dynamic and static IPv4 EID-to-RLOC map-cache entries. When no IPv4 EID or IPv4 EID prefix is specified, summary information is listed for all current dynamic and static IPv4 EID-to-RLOC map-cache entries. When an IPv4 EID or IPv4 EID prefix is included, information is listed for the longest-match lookup in the cache. When the **detail** option is used, detailed (rather than summary) information related to all current dynamic and static IPv4 EID-to-RLOC map-cache entries is displayed.

### Examples

The following sample output from the **show lisp instance-id ipv4 map-cache** command (without the use of an IPv4 EID or IPv4 EID prefix) displays a summary list of current dynamic and static IPv4 EID-to-RLOC map-cache entries. The display shows IPv4 EID prefix and associated information.

```
Router# show lisp instance-id ipv4 map-cache

LISP IPv4 Mapping Cache, 2 entries
0.0.0.0/0, uptime: 00:00:17, expires: never, via static
  Negative cache entry, action: send-map-request
192.168.2.0/24, uptime: 00:00:02, expires: 23:59:54, via map-reply, complete
Locator  Uptime   State    Pri/Wgt
10.0.0.6 00:00:02 up       1/100
10.1.0.6 00:00:02 admin-down 255/0
```

The following sample output from the **show lisp instance-id ipv4 map-cache detail** command displays a detailed list of current dynamic and static IPv4 EID-to-RLOC map-cache entries.

**show lisp instance-id ipv4 map-cache**

```

Router# show lisp instance-id ipv4 map-cache detail

LISP IPv4 Mapping Cache, 2 entries

0.0.0.0/0, uptime: 00:00:41, expires: never, via static
  State: send-map-request, last modified: 00:00:41, map-source: local
  Idle, Packets out: 0
  Negative cache entry, action: send-map-request
192.168.2.0/24, uptime: 00:00:26, expires: 23:59:31, via map-reply, complete
  State: complete, last modified: 00:00:26, map-source: 10.0.0.6
  Active, Packets out: 0
Locator  Uptime  State      Pri/Wgt
10.0.0.6  00:00:26 up          1/100
  Last up-down state change:      never, state change count: 0
  Last priority / weight change:   never/never
  RLOC-probing loc-status algorithm:
  Last RLOC-probe sent:           never
10.1.0.6  00:00:26 admin-down 255/0
  Last up-down state change:      never, state change count: 0
  Last priority / weight change:   never/never
  RLOC-probing loc-status algorithm:
  Last RLOC-probe sent:           never

```

The following sample output from the **show lisp instance-id ipv4 map-cache** command with a specific IPv4 EID prefix displays detailed information associated with that IPv4 EID-prefix entry.

```

Router# show lisp instance-id ipv4 map-cache 192.168.2.0/24

LISP IPv4 Mapping Cache, 2 entries

192.168.2.0/24, uptime: 00:01:01, expires: 23:58:56, via map-reply, complete
  State: complete, last modified: 00:01:01, map-source: 10.0.0.6
  Active, Packets out: 0
Locator  Uptime  State      Pri/Wgt
10.0.0.6  00:01:01 up          1/100
  Last up-down state change:      never, state change count: 0
  Last priority / weight change:   never/never
  RLOC-probing loc-status algorithm:
  Last RLOC-probe sent:           never
10.1.0.6  00:01:01 admin-down 255/0
  Last up-down state change:      never, state change count: 0
  Last priority / weight change:   never/never
  RLOC-probing loc-status algorithm:
  Last RLOC-probe sent:           never

```

**Related Commands**

Command	Description
<b>show ip lisp forwarding</b>	Displays LISP local or remote IPv4 EID-prefix information.



# show ip lisp route-import database



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp instance-id [0-1677200] ipv4 route-import database**.

To display the current IPv4 Routing Information Base (RIB) routes imported into Locator ID Separation Protocol (LISP) to define local endpoint identifier (EID) database entries, use the **show ip lisp route-import database** command in privileged EXEC mode.

```
show ip lisp [router-lisp-id] [instance-id iid] route-import database [ipv4-address | ipv4-prefix
| eid-table {vrf eid-table-vrf-name | default } ]
```

Syntax Description	
<i>router-lisp-id</i>	(Optional) Router LISP ID. Range: 0 to 65520
<b>instance-id</b> <i>iid</i>	(Optional) Limits the output of the command to the referenced instance ID. Range: 0 to 16777214
<i>ipv4-address</i>	(Optional) IPv4 address to longest-match against imported routes.
<i>ipv4-prefix</i>	(Optional) IPv4 imported route prefix.
<b>eid-table</b>	(Optional) Limits the output of the command to the referenced EID table.
<b>vrf</b> <i>eid-table-vrf-name</i>	VRF name.
<b>default</b>	Default VRF.

**Command Modes** Privileged EXEC (#)

Command History	Release	Modification
	15.4(2)T	This command was introduced.
	3.12.0S	This command was integrated into Cisco IOS XE Release 3.12.0S.

**Usage Guidelines** When the optional *router-lisp-id* argument is used, the **show ip lisp route-import database** command displays the IPv4 LISP configuration status for the specified router LISP instantiation. When used without the optional argument, the command displays the IPv4 LISP configuration status for the local device for the default router LISP ID.

When the optional **instance-id** *i-id* keyword and argument pair is used, the **show ip lisp route-import database** command displays the IPv4 LISP configuration status for the local device for the specified LISP instance ID associated with a VRF. When used without the optional **instance-id** keyword, the command displays the IPv4 LISP configuration status for the local device for all LISP configurations present on the device.

When used with the optional *ipv4-address* argument, the **show ip lisp route-import database** command displays the IPv4 LISP configuration status for the local device for the IPv4 address to longest match against imported routes. When used with the optional *ipv4-prefix* argument, the command displays the IPv4 LISP configuration status for the local device for the IPv4 imported route prefix. When used without the optional *ipv4-address* or *ipv4-prefix* arguments, the command displays the IPv4 LISP configuration status for the local device for all IPv4 addresses or prefixes that are configured on the device.

### Example

The following example shows how to display the current IPv4 RIB routes imported into LISP to define local EID database entries using the **show ip lisp route-import database** command:

```
Device# show ip lisp route-import database

LISP IPv4 imported routes for EID-table default (IID 0)
Config: 1, Entries: 8 (limit 1000)
Prefix                Uptime      Source  Map-cache  State
10.1.0.0/16           00:07:52   ospf 10  installed
10.10.1.0/24          00:14:02   ospf 10  installed
10.10.2.0/24          00:14:02   ospf 10  installed
10.10.3.0/24          00:14:02   ospf 10  installed
10.10.4.0/24          00:14:02   ospf 10  installed
10.10.5.0/24          00:14:02   ospf 10  installed
172.16.1.0/24         00:11:52   ospf 10  installed
192.168.20.0/24       00:11:52   ospf 10  installed
```

### Related Commands

Command	Description
<b>show ip lisp route-import map-cache</b>	Displays the current IPv4 RIB routes imported into LISP to define EID address space in map cache.
<b>show ipv6 lisp route-import database</b>	Displays the current IPv6 RIB routes imported into LISP to define local EID database entries.
<b>show ipv6 lisp route-import map-cache</b>	Displays the current IPv6 RIB routes imported into LISP to define EID address space in map cache.

## show lisp instance-id ipv4 route-import database

To display the current IPv4 Routing Information Base (RIB) routes imported into Locator ID Separation Protocol (LISP) to define local endpoint identifier (EID) database entries, use the **show ip lisp instance-id [0-16777200]ipv4route-import database** command in privileged EXEC mode.

```
show lisp [ router-lisp-id ] [ instance-id iid ] ipv4 route-import database [ ipv4-address
| ipv4-prefix | eid-table { vrf eid-table-vrf-name | default } ]
```

Syntax Description		
<i>router-lisp-id</i>	(Optional) Router LISP ID. Range: 0 to 65520	
<b>instance-id</b> <i>iid</i>	(Optional) Limits the output of the command to the referenced instance ID. Range: 0 to 16777214	
<i>ipv4-address</i>	(Optional) IPv4 address to longest-match against imported routes.	
<i>ipv4-prefix</i>	(Optional) IPv4 imported route prefix.	
<b>eid-table</b>	(Optional) Limits the output of the command to the referenced EID table.	
<b>vrf</b> <i>eid-table-vrf-name</i>	VRF name.	
<b>default</b>	Default VRF.	

**Command Modes** Privileged EXEC (#)

Command History	Release	Modification
	Cisco IOS XE Dublin 17.11.1a	This command was introduced.

**Usage Guidelines** When the optional *router-lisp-id* argument is used, the **show lisp instance-id [0-16777200]route-import database** command displays the IPv4 LISP configuration status for the specified router LISP instantiation. When used without the optional argument, the command displays the IPv4 LISP configuration status for the local device for the default router LISP ID.

When the optional **instance-id** *i-id* keyword and argument pair is used, the **show lisp instance-id [0-16777200]ipv4route-import database** command displays the IPv4 LISP configuration status for the local device for the specified LISP instance ID associated with a VRF. When used without the optional **instance-id** keyword, the command displays the IPv4 LISP configuration status for the local device for all LISP configurations present on the device.

When used with the optional *ipv4-address* argument, the **show lisp instance-id [0-16777200]route-import database** command displays the IPv4 LISP configuration status for the local device for the IPv4 address to longest match against imported routes. When used with the optional *ipv4-prefix* argument, the command displays the IPv4 LISP configuration status for the local device for the IPv4 imported route prefix. When used

**show lisp instance-id ipv4 route-import database**

without the optional *ipv4-address* or *ipv4-prefix* arguments, the command displays the IPv4 LISP configuration status for the local device for all IPv4 addresses or prefixes that are configured on the device.

The following example shows how to display the current IPv4 RIB routes imported into LISP to define local EID database entries using the **show lisp instance-id [0-16777200]ipv4route-import database** command:

```
Device# show lisp instance-id [0-16777200] ipv4 route-import database

LISP IPv4 imported routes for EID-table default (IID 0)
Config: 1, Entries: 8 (limit 1000)
Prefix                Uptime      Source  Map-cache  State
10.1.0.0/16           00:07:52   ospf 10  installed
10.10.1.0/24          00:14:02   ospf 10  installed
10.10.2.0/24          00:14:02   ospf 10  installed
10.10.3.0/24          00:14:02   ospf 10  installed
10.10.4.0/24          00:14:02   ospf 10  installed
10.10.5.0/24          00:14:02   ospf 10  installed
172.16.1.0/24         00:11:52   ospf 10  installed
192.168.20.0/24      00:11:52   ospf 10  installed
```

**Related Commands**

Command	Description
<b>show ip lisp route-import map-cache</b>	Displays the current IPv4 RIB routes imported into LISP to define EID address space in map cache.
<b>show ipv6 lisp route-import database</b>	Displays the current IPv6 RIB routes imported into LISP to define local EID database entries.
<b>show ipv6 lisp route-import map-cache</b>	Displays the current IPv6 RIB routes imported into LISP to define EID address space in map cache.

# show ip lisp route-import map-cache



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp instance-id [0-1677200] ipv4 route-import map-cache**.

To display the current IPv4 Routing Information Base (RIB) routes imported into Locator ID Separation Protocol (LISP) to define endpoint identifier (EID) address space in map cache, use the **show ip lisp route-import map-cache** command in privileged EXEC mode.

```
show ip lisp [router-lisp-id] [instance-id iid] route-import map-cache [ipv4-address | ipv4-prefix
| eid-table {vrf eid-table-vrf-name | default} ]
```

## Syntax Description

<i>router-lisp-id</i>	(Optional) Router LISP ID. Range: 0 to 65520
<b>instance-id</b> <i>iid</i>	(Optional) Limits the output of the command to the referenced instance ID. Range: 0 to 1677214
<i>ipv4-address</i>	(Optional) IPv4 address to longest-match against imported routes.
<i>ipv4-prefix</i>	(Optional) IPv4 imported route prefix.
<b>eid-table</b>	(Optional) Limits the output of the command to the referenced EID table.
<b>vrf</b> <i>eid-table-vrf-name</i>	VRF name.
<b>default</b>	Default VRF.

## Command Modes

Privileged EXEC (#)

## Command History

### Release Modification

15.4(2)T This command was introduced.

3.12.0S This command was integrated into Cisco IOS XE Release 3.12.0S.

## Usage Guidelines

When the optional *router-lisp-id* argument is used, the **show ip lisp route-import map-cache** command displays the IPv4 LISP configuration status for the specified router LISP instantiation. When used without the optional argument, the command displays the IPv4 LISP configuration status for the local device for the default router LISP ID.

When the optional **instance-id** keyword is used with the *iid* argument, the **show ip lisp route-import map-cache** command displays the IPv4 LISP configuration status for the local device for the specified LISP instance ID associated with a VRF. When used without the optional **instance-id** keyword, the command displays the IPv4 LISP configuration status for the local device for all LISP configurations present on the device.

When used with the optional *ipv4-address* or *ipv4-prefix* arguments, the **show ip lisp route-import map-cache** command displays the IPv4 LISP configuration status for the local device for IPv4 address to longest match against imported routes or IPv4 imported route prefix respectively. When used without either of the optional *ipv4-address* or *ipv4-prefix* arguments, the command displays the IPv4 LISP configuration status for the local device for all IPv4 addresses or prefixes that are configured on the device.

### Example

The following example shows how to display the current IPv4 RIB routes imported into LISP to define EID address space in map-cache using the **show ip lisp route-import map-cache** command:

```
Device# show ip lisp route-import map-cache

LISP IPv4 imported routes for EID-table default (IID 0)
Config: 1, Entries: 6 (limit 1000)
Prefix                Uptime      Source      Map-cache  State
10.1.0.0/16           00:07:52   bgp 64496   installed
10.2.0.0/16           00:21:31   bgp 64496   installed
10.3.0.0/16           00:21:31   bgp 64496   installed
10.4.0.0/16           00:21:31   bgp 64496   installed
172.16.1.0/24         00:11:52   bgp 64496   installed
192.168.20.0/24      00:11:52   bgp 64496   installed
```

### Related Commands

Command	Description
<b>show ip lisp route-import database</b>	Displays the current IPv4 RIB routes imported into LISP to define local EID database entries.
<b>show ipv6 lisp route-import database</b>	Displays the current IPv6 RIB routes imported into LISP to define local EID database entries.
<b>show ipv6 lisp route-import map-cache</b>	Displays the current IPv6 RIB routes imported into LISP to define EID address space in map-cache.

## show lisp instance-id ipv4 route-import map-cache

To display the current IPv4 Routing Information Base (RIB) routes imported into Locator ID Separation Protocol (LISP) to define endpoint identifier (EID) address space in map cache, use the **show lisp instance-id [0-16777200] route-import map-cache** command in privileged EXEC mode.

```
show lisp [ router-lisp-id ] [ instance-id iid ] ipv4 route-import map-cache [
ipv4-address | ipv4-prefix | eid-table { vrf eid-table-vrf-name | default } ]
```

### Syntax Description

<i>router-lisp-id</i>	(Optional) Router LISP ID. Range: 0 to 65520
<b>instance-id</b> <i>iid</i>	(Optional) Limits the output of the command to the referenced instance ID. Range: 0 to 16777214
<i>ipv4-address</i>	(Optional) IPv4 address to longest-match against imported routes.
<i>ipv4-prefix</i>	(Optional) IPv4 imported route prefix.
<b>eid-table</b>	(Optional) Limits the output of the command to the referenced EID table.
<b>vrf</b> <i>eid-table-vrf-name</i>	VRF name.
<b>default</b>	Default VRF.

### Command Modes

Privileged EXEC (#)

### Command History

Release	Modification
Cisco IOS XE Dublin 17.11.1a	This command was introduced.

### Usage Guidelines

When the optional *router-lisp-id* argument is used, the **show lisp instance-id [0-16777200]ipv4route-import map-cache** command displays the IPv4 LISP configuration status for the specified router LISP instantiation. When used without the optional argument, the command displays the IPv4 LISP configuration status for the local device for the default router LISP ID.

When the optional **instance-id** keyword is used with the *iid* argument, the **show lisp instance-id [0-16777200]route-import map-cache** command displays the IPv4 LISP configuration status for the local device for the specified LISP instance ID associated with a VRF. When used without the optional **instance-id** keyword, the command displays the IPv4 LISP configuration status for the local device for all LISP configurations present on the device.

When used with the optional *ipv4-address* or *ipv4-prefix* arguments, the **show lisp instance-id [0-16777200]ipv4route-import map-cache** command displays the IPv4 LISP configuration status for the local device for IPv4 address to longest match against imported routes or IPv4 imported route prefix respectively. When used without either of the optional *ipv4-address* or *ipv4-prefix* arguments, the command displays the IPv4 LISP configuration status for the local device for all IPv4 addresses or prefixes that are configured on the device.

**Example**

The following example shows how to display the current IPv4 RIB routes imported into LISP to define EID address space in map-cache using the **show ip lisp route-import map-cache** command:

```
Device# show lisp instance-id ipv4 route-import map-cache

LISP IPv4 imported routes for EID-table default (IID 0)
Config: 1, Entries: 6 (limit 1000)
Prefix          Uptime      Source      Map-cache  State
10.1.0.0/16     00:07:52   bgp 64496   installed
10.2.0.0/16     00:21:31   bgp 64496   installed
10.3.0.0/16     00:21:31   bgp 64496   installed
10.4.0.0/16     00:21:31   bgp 64496   installed
172.16.1.0/24   00:11:52   bgp 64496   installed
192.168.20.0/24 00:11:52   bgp 64496   installed
```

**Related Commands**

Command	Description
<b>show ip lisp route-import database</b>	Displays the current IPv4 RIB routes imported into LISP to define local EID database entries.
<b>show ipv6 lisp route-import database</b>	Displays the current IPv6 RIB routes imported into LISP to define local EID database entries.
<b>show ipv6 lisp route-import map-cache</b>	Displays the current IPv6 RIB routes imported into LISP to define EID address space in map-cache.



# show ip lisp statistics



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp instance-id [0-16777200] ipv4 statistics**.

To display Locator/ID Separation Protocol (LISP) IPv4 address-family packet count statistics, use the **show ip lisp statistics** command in privileged EXEC mode.

## show ip lisp statistics

**Syntax Description** This command has no arguments or keywords.

**Command Modes** Privileged EXEC (#)

Command History	Release	Modification
	15.1(1)XB1	This command was introduced.
	Cisco IOS XE Release 2.5.1XA	This command was integrated into Cisco IOS XE Release 2.5.1XA.
	Cisco IOS XE Release 3.3.0S	This command was integrated into Cisco IOS XE Release 3.3.0S.
	15.1(4)M	This command was integrated into Cisco IOS Release 15.1(4)M.

**Usage Guidelines** This command is used to display IPv4 LISP statistics related to packet encapsulations, de-encapsulations, map requests, map replies, map registers, and other LISP-related packets.

## Examples

The following sample output from the **show ip lisp statistics** command displays the current LISP IPv4 address family statistics. The output varies, depending on the LISP features configured and the state of various LISP components:

```
Router# show ip lisp statistics

LISP Statistics - last cleared: never
Control Packets:
  Map-Requests in/out:                76/35
  Encapsulated Map-Requests in/out:   76/35
  RLOC-probe Map-Requests in/out:     0/0
  Map-Reply records in/out:           35/76
  Authoritative records in/out:       0/76
  Non-authoritative records in:        35
  Negative records in:                 35
  RLOC-probe records in/out:          0/0
  Map-Registers out:                  626
Errors:
  Map-Request format errors:          0
  Map-Reply format errors:             0
  Map-Reply spoof alerts:              0
```

**show ip lisp statistics**

```
Mapping record TTL alerts:          0
Cache Related:
Cache entries created/deleted:      72/69
Number of EID-prefixes in map-cache: 3
Number of negative entries in map-cache: 3
Total number of RLOCs in map-cache: 0
Average RLOCs per EID-prefix:      0
Forwarding:
Number of data signals processed:    35 (+ dropped 0)
Number of reachability reports:     0 (+ dropped 0)
```

**Related Commands**

Command	Description
<b>show ip lisp</b>	Displays the IPv4 LISP configuration status for the local device.

# show lisp ipv4 statistics



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp instance-id [0-16777200] ipv4 statistics**.

To display Locator/ID Separation Protocol (LISP) IPv4 address-family packet count statistics, use the **show lisp ipv4 statistics** command in privileged EXEC mode.

**show lisp ipv4 statistics**

**Syntax Description** This command has no arguments or keywords.

**Command Modes** Privileged EXEC (#)

Command History	Release	Modification
	Cisco IOS XE Dublin 17.11.1a	This command was introduced.

**Usage Guidelines** This command is used to display IPv4 LISP statistics related to packet encapsulations, de-encapsulations, map requests, map replies, map registers, and other LISP-related packets.

## Examples

The following sample output from the **show lisp ipv4 statistics** command displays the current LISP IPv4 address family statistics. The output varies, depending on the LISP features configured and the state of various LISP components:

```
Router# show lisp ipv4 statistics

LISP Statistics - last cleared: never
Control Packets:
  Map-Requests in/out:                76/35
  Encapsulated Map-Requests in/out:   76/35
  RLOC-probe Map-Requests in/out:     0/0
  Map-Reply records in/out:           35/76
  Authoritative records in/out:       0/76
  Non-authoritative records in:        35
  Negative records in:                 35
  RLOC-probe records in/out:          0/0
  Map-Registers out:                   626
Errors:
  Map-Request format errors:          0
  Map-Reply format errors:             0
  Map-Reply spoof alerts:              0
  Mapping record TTL alerts:           0
Cache Related:
  Cache entries created/deleted:      72/69
  Number of EID-prefixes in map-cache: 3
  Number of negative entries in map-cache: 3
  Total number of RLOCs in map-cache: 0
  Average RLOCs per EID-prefix:       0
```

**show lisp ipv4 statistics**

```
Forwarding:
  Number of data signals processed:      35 (+ dropped 0)
  Number of reachability reports:       0 (+ dropped 0)
```

**Related Commands**

<b>Command</b>	<b>Description</b>
<b>show ip lisp</b>	Displays the IPv4 LISP configuration status for the local device.

# show ipv6 lisp



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp service ipv6** or **show lisp instance-id [0-16777200] ipv6**.

To display the Locator/ID Separation Protocol (LISP) IPv6 configuration status, use the **show ipv6 lisp** command in privileged EXEC mode.

```
show ipv6 lisp [{router-lisp-id}]
```

## Syntax Description

<i>router-lisp-id</i>	(Optional) router lisp instantiation id (0-15)
-----------------------	--

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
15.1(1)XB	This command was introduced.
15.1(1)XB1	This command was modified.
Cisco IOS XE Release 2.5.1XA	This command was integrated into Cisco IOS XE Release 2.5.1XA.
15.1(1)XB2	This command was modified.
Cisco IOS XE Release 2.5.1XB	This command was modified.
15.1(4)M	This command was integrated into Cisco IOS Release 15.1(4)M and modified to include the <b>locator-table</b> keyword.
Cisco IOS XE Release 3.3S	This command was integrated into Cisco IOS XE Release 3.3S and modified to include the <b>locator-table</b> keyword.

## Usage Guidelines

When used without the optional router LISP ID value, the **show ipv6 lisp** command displays the IPv6 LISP configuration status for the local device for the default router LISP instantiation. When the *router-lisp-id* argument is used, the command displays the IPv6 LISP configuration status for the specified router LISP instantiation.

## Examples

The following sample output from the **show ipv6 lisp** command displays information about the current IPv6 LISP configuration status. The output varies, depending on the LISP features configured:

```
Router# show ipv6 lisp

Ingress Tunnel Router (ITR):      enabled
Egress Tunnel Router (ETR):      enabled
Proxy-ITR Router (PITR):        disabled
```

```

Proxy-ETR Router (PETR):      disabled
Map Server (MS):             disabled
Map Resolver (MR):           disabled
Map-Request source:          2001:DB8:A:2::1
ITR Map-Resolver:            10.0.100.2
ETR Map-Server(s):           10.0.100.2 (00:00:07)
ETR accept mapping data:     disabled, verify disabled
ETR map-cache TTL:           1d00h
Locator Status Algorithms:
  RLOC-probe algorithm:      disabled
Static mappings configured:   0
Map-cache size/limit:         1/1000
Map-cache activity check period: 60 secs

```

The table below describes the significant fields shown in the display.

### show ipv6 lisp Field Descriptors

**Table 2: ipv6 lisp Field Descriptions**

Field	Description
Ingress Tunnel Router (ITR)	Indicates whether the router is configured as an ITR. See the <b>ipv6 itr</b> command.
Egress Tunnel Router (ETR)	Indicates whether the router is configured as an ETR. See the <b>ipv6 etr</b> command.
Proxy-ITR (PITR)	Indicates whether the router is configured as a PITR. See the <b>ipv6 proxy-itr</b> command.
Proxy-ETR (PETR)	Indicates whether the router is configured as a PETR. See the <b>ipv6 proxy-etr</b> command.
Map Server (MS)	Indicates whether the router is configured as a map server. See the <b>ipv6 map-server</b> command.
Map Resolver (MR)	Indicates whether the router is configured as a map resolver. See the <b>ipv6 map-resolver</b> command.
Map-Request source	Identifies the IPv6 address used as the source in Map Request messages.
ITR Map-Resolver	Identifies the configured ITR map resolver. See the <b>ipv6 itr map-resolver</b> command.
ETR Map-Server(s)	Identifies the configured ETR map servers. See the <b>ipv6 etr map-server</b> command.
ITR Solicit Map Request (SMR)	Indicates whether SMRs are accepted and processed. See the <b>ipv6 solicit-map-request</b> command.
ETR accept mapping data	Indicates whether the ETR is configured to cache the mapping data contained in a map request. See the <b>ipv6 etr accept-map-request-mapping</b> command.

Field	Description
ETR map-cache TTL	Identifies the current ETR map-cache TTL. See the <b>ipv6 etr map-cache-ttl</b> command.
RLOC-probe algorithm	Indicates whether the locator reachability algorithm RLOC probing is enabled. See the <b>loc-reach-algorithm</b> command.
Static mappings configured	Indicates the number of static cache-map entries configured. See the <b>map-cache</b> command.
Map-cache size/limit	Indicates the number of entries currently in the map cache and indicates the limit value. See the <b>ipv6 map-cache-limit</b> command.
Map-cache activity check period	Indicates how often the control plane checks the map cache for outbound usage activity.
Map-database size	Indicates the number of entries currently in the map-database. See the <b>database-mapping</b> command.
Persistent map-cache	Indicates the persistent map-cache timer interval, next use, and storage location. See the <b>ipv6 map-cache-persistent</b> command.
ITR use proxy ETR RLOC configuration	When configured, indicates that the router uses PETR services and lists the PETR locator. See the <b>ipv6 use-petr</b> command.

The following sample output from the **show ipv6 lisp** command displays information about the current IPv6 LISP configuration status when a LISP instantiation has been created using the **router lisp router-lisp-id** command and the **locator-table** command. Below, the results shown are based on router LISP 6 and locator table VRF named Cust-1. (Other output varies depending on the LISP features configured.)

```
Router# show ipv6 lisp 6

Information applicable to all EID instances:
Router-lisp ID: 6
Locator table: vrf Cust-1
Ingress Tunnel Router (ITR): enabled
---<more>---
```

#### Related Commands

Command	Description
<b>database-mapping</b>	Configures an IPv4 or IPv6 EID-to-RLOC mapping relationship and its associated traffic policy for LISP.
<b>eid-table</b>	Configures a LISP instance-id for association with a VRF table or default table through which the EID address space is reachable.
<b>ipv6 etr</b>	Configures a router to act as an IPv6 LISP ETR.

Command	Description
<b>ipv6 etr map-cache-ttl</b>	Configures the TTL value inserted into LISP IPv6 map-reply messages.
<b>ipv6 etr map-server</b>	Configures the IPv4 or IPv6 locator address of the LISP map server to be used by the ETR when registering for IPv4 EIDs.
<b>ipv6 itr</b>	Configures the router to act as an IPv6 LISP ITR.
<b>ipv6 itr map-resolver</b>	Configures the IPv6 locator address of the LISP map resolver to be used by the ITR when sending map requests for IPv6 EID-to-RLOC mapping resolution.
<b>ipv6 lisp etr accept-map-request-mapping</b>	Configures an ETR to cache IPv6 mapping data contained in a map-request message.
<b>ipv6 lisp source-locator</b>	Configures a source locator to be used for IPv6 LISP encapsulated packets.
<b>ipv6 map-cache-limit</b>	Configures the maximum number of IPv6 LISP map-cache entries allowed to be stored by the router.
<b>ipv6 map-cache-persistent</b>	Configures how often, in minutes, an ITR should save its dynamically learned IPv6 map-cache entries to a file in flash.
<b>ipv6 map-resolver</b>	Configures the router to act as an IPv6 LISP map resolver.
<b>ipv6 map-server</b>	Configures the router to act as an IPv6 LISP map server.
<b>ipv6 solicit-map-request ignore</b>	Configures an ITR to ignore an IPv6 Map Request message that has the solicit-map-request (SMR) bit set.
<b>ipv6 proxy-etr</b>	Configures the router to act as an IPv6 LISP PETR.
<b>ipv6 proxy-itr</b>	Configures the router to act as an IPv6 LISP PITR.
<b>ipv6 use-petr</b>	Configures a router to use an IPv6 LISP PETR.
<b>locator-table</b>	Configures the association of a VRF table through which the routing locator address space is reachable to a router LISP instantiation.
<b>map-cache</b>	Configures a static IPv4 or IPv6 EID-to-RLOC mapping relationship and its associated traffic policy, or statically configures the packet handling behavior associated with a specified destination IPv4 or IPv6 EID prefix.
<b>router lisp</b>	Enters LISP configuration mode and configures LISP commands on a router.
<b>show ipv6 lisp locator-table</b>	Displays the association of a VRF table through which the routing locator address space is reachable to a router LISP instantiation.



# show ipv6 lisp database



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp instance-id [0-16777200] ipv6 database**.

To display Locator/ID Separation Protocol (LISP) Egress Tunnel Router (ETR) configured local IPv6 EID prefixes and associated locator sets, use the **show ipv6 lisp database** command in privileged EXEC mode.

**show ipv6 lisp database** [{eid-prefix}]

<b>Syntax Description</b>	<b>eid-prefix</b>	(Optional) Displays one of any IPv6 EID prefixes configured using the <b>database-mapping</b> command.
---------------------------	-------------------	--

**Command Modes** Privileged EXEC (#)

<b>Command History</b>	<b>Release</b>	<b>Modification</b>
	15.1(1)XB1	This command was introduced.
	Cisco IOS XE Release 2.5.1XA	This command was integrated into Cisco IOS XE Release 2.5.1XA.
	Cisco IOS XE Release 3.3.0S	This command was integrated into Cisco IOS XE Release 3.3.0S.
	15.1(4)M	This command was integrated into Cisco IOS Release 15.1(4)M.

**Usage Guidelines** This command is used on LISP ETR devices to display the configured local IPv6 EID prefixes and associated locator sets.

## Examples

The following sample output from the **show ipv6 lisp database** command displays the configured IPv6 EID-prefix blocks and associated locator sets and the configured IPv6 endpoint identifier-to-routing locator (EID-to-RLOC) database mappings:

```
Router# show running-config
.
.
!
database-mapping 2610:D0:1209::/48 172.16.156.222 priority 1 weight 100
!
Router# show ipv6 lisp database

LISP ETR IPv6 Mapping Database, LSBs: 0x1

EID-prefix: 2610:D0:1209::/48
  172.16.156.222, priority: 1, weight: 100, state: up, local
```

---

**Related Commands**

Command	Description
<b>database-mapping</b>	Configures an IPv6 EID-to-RLOC mapping relationship and its associated traffic policy.

## show lisp instance-id ipv6 database

To display the negative prefix hole in the LISP ALT for an EID within a specified instance-id, use the **show lisp instance-id [0-16777200] ipv6 database** command in privileged EXEC mode.

```
show lisp instance-id [0-16777200] ipv6 database
```

### Syntax Description

There is no syntax description table for this command.

### Command Modes

Privileged EXEC (#)

### Command Modes

Privileged EXEC (#)

### Command History

Release	Modification
Cisco IOS XE Dublin 17.11.1a	This command was introduced.

### Usage Guidelines

This command is used on LISP ETR devices to display the configured local IPv6 EID prefixes and associated locator sets.

### Examples

The following sample output from the **showlispinstance-id [0-16777200]ipv6database** command displays the configured IPv6 EID-prefix blocks and associated locator sets and the configured IPv6 endpoint identifier-to-routing locator (EID-to-RLOC) database mappings:

```
Router# show running-config
.
.
!
database-mapping 2610:D0:1209::/48 172.16.156.222 priority 1 weight 100
!
Router# show lisp instance-id [0-16777200] ipv6 database

LISP ETR IPv6 Mapping Database, LSBs: 0x1

EID-prefix: 2610:D0:1209::/48
  172.16.156.222, priority: 1, weight: 100, state: up, local
```

### Related Commands

Command	Description
<b>database-mapping</b>	Configures an IPv6 EID-to-RLOC mapping relationship and its associated traffic policy.

# show ipv6 lisp forwarding



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp instance-id [0-16777200] ipv6 forwarding**.

To display Locator/ID Separation Protocol (LISP) IPv6 endpoint identifier (EID)-prefix forwarding information, use the **show ipv6 lisp forwarding** command in privileged EXEC mode.

**show ipv6 lisp forwarding** {**eid** {**local** | **remote** [**detail**]} | **state**}

## Syntax Description

<b>eid</b>	Displays information related to EID prefixes (local or remote)
<b>local</b>	Displays locally configured EID prefixes.
<b>remote</b>	Displays forwarding action and Locator status bits for dynamically learned EID-prefix blocks, and the number of packets and total bytes encapsulated
<b>detail</b>	(Optional) Displays detailed information associated with each remote EID prefix
<b>state</b>	Displays information about the LISP module forwarding state

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
15.1(1)XB1	This command was introduced.
Cisco IOS XE Release 2.5.1XA	This command was integrated into Cisco IOS XE Release 2.5.1XA
Cisco IOS XE Release 3.3.0S	This command was integrated into Cisco IOS XE Release 3.3.0S.
15.1(4)M	This command was integrated into Cisco IOS Release 15.1(4)M.

## Usage Guidelines

This command is used to display information for either local or remote IPv6 EID-prefixes. Local IPv6 EID-prefixes are those for which the router is authoritative and added via the **database-mapping** command. Remote IPv6 EID-prefixes are those for remote sites and learned dynamically through map-reply information or via map-request messages when the **ipv6 etr accept-map-request-mapping** command is configured.

## Examples

The following sample output from the **show ipv6 lisp forwarding eid local** command displays local IPv6 EID-prefix information.

```
Router# show ipv6 lisp forwarding eid local

Prefix
```

```
2001:DB8:AA::/48
2001:DB8:BB::/48
```

The following sample output from the **show ipv6 lisp forwarding eid remote** command displays summary remote IPv6 EID-prefix information. Summary information is displayed when the keyword **detail** is not used. The display shows the EID prefix, associated locator status bits, and total encapsulated packets and bytes for each remote IPv6 EID prefix.

```
Router# show ipv6 lisp forwarding eid remote

Prefix          Fwd action  Locator status bits
::/0            signal      0x00000000
  packets/bytes  0/0
2001:DB8:AB::/48 encap        0x00000001
  packets/bytes  25/2150
```

The following sample output from the **show ipv6 lisp forwarding eid remote detail** command displays detailed remote IPv6 EID-prefix information by adding the **detail** keyword. The display shows the EID-prefix, associated locator status bits, and total encapsulated packets/bytes for each remote IPv6 EID prefix.

```
Router# show ipv6 lisp forwarding eid remote detail

Prefix          Fwd action  Locator status bits
::/0            signal      0x00000000
  packets/bytes  0/0
  path list 0729CE78, flags 0x49, 3 locks, per-destination
  ifnums:
    LISP0(14)
  1 path
    path 0729D4E0, path list 0729CE78, share 1/1, type attached prefix, for IPv6
    attached to LISP0, adjacency glean for LISP0
  1 output chain
    chain[0]: glean for LISP0
2001:DB8:AB::/48 encap        0x00000001
  packets/bytes  25/2150
  path list 06BFA050, flags 0x49, 3 locks, per-destination
  ifnums:
    LISP0(14): 10.0.0.6
  1 path
    path 06E8C5B0, path list 06BFA050, share 100/100, type attached nexthop, for IPv6
    nexthop 10.0.0.6 LISP0, adjacency IPV6 midchain out of LISP0, addr 10.0.0.6 07374688
  1 output chain
Prefix          Fwd action  Locator status bits
  chain[0]: IPV6 midchain out of LISP0, addr 10.0.0.6 07374688 IP adj out of Ethernet0/0,
  addr 10.0.0.2 0620D8A8
```

The following sample output from the **show ipv6 lisp forwarding state** command displays detailed information about the state of the LISP process forwarding state. (Both IPv4 and IPv6 information is presented).

```
Router# show ipv6 lisp forwarding state

LISP forwarding state for EID table IPv4:Default
EID VRF          Default (0x0)
  IPv4
    Configured roles  ITR|ETR
    Active roles      ITR|ETR
    EID table         IPv4:Default
    ALT table         <null>
    Locator status bits 0x00000001
```

## show ipv6 lisp forwarding

```

IPv6
  Configured roles      ITR|ETR
  Active roles         ITR|ETR
  EID table            IPv6:Default
  ALT table            <null>
  Locator status bits  0x00000001
  RLOC transport VRF   Default (0x0)
  IPv4 RLOC table      IPv4:Default
  IPv6 RLOC table      IPv6:Default
  LISP virtual interface LISP0

```

## Related Commands

Command	Description
<b>database-mapping</b>	Configures an IPv6 EID-to-RLOC mapping relationship and its associated traffic policy.
<b>ipv6 lisp etr accept-map-request-mapping</b>	Configures an ETR to cache IPv6 mapping data contained in a map-request message.
<b>show ipv6 lisp map-cache</b>	Displays the current dynamic and static IPv6 EID-to-RLOC map-cache entries.

## show lisp instance-id ipv6 forwarding

To display Locator/ID Separation Protocol (LISP) IPv6 endpoint identifier (EID)-prefix forwarding information, use the **show lisp instance-id [0-16777200] forwarding** command in privileged EXEC mode.

```
show lisp instance-id [0-16777200] ipv6 forwarding { eid { local | remote [detail] } | state }
```

Syntax Description	eid	Displays information related to EID prefixes (local or remote)
	local	Displays locally configured EID prefixes.
	remote	Displays forwarding action and Locator status bits for dynamically learned EID-prefix blocks, and the number of packets and total bytes encapsulated
	detail	(Optional) Displays detailed information associated with each remote EID prefix
	state	Displays information about the LISP module forwarding state

**Command Modes** Privileged EXEC (#)

Command History	Release	Modification
	Cisco IOS XE Dublin 17.11.1a	This command was introduced.

**Usage Guidelines** This command is used to display information for either local or remote IPv6 EID-prefixes. Local IPv6 EID-prefixes are those for which the router is authoritative and added via the **database-mapping** command. Remote IPv6 EID-prefixes are those for remote sites and learned dynamically through map-reply information or via map-request messages when the **ipv6 etr accept-map-request-mapping** command is configured.

### Examples

The following sample output from the **show lisp instance-id [0-16777200] ipv6 forwarding eid local** command displays local IPv6 EID-prefix information.

```
Router# show lisp instance-id [0-16777200] ipv6 forwarding eid local

Prefix
2001:DB8:AA::/48
2001:DB8:BB::/48
```

The following sample output from the **show lisp instance-id [0-16777200] forwarding eid remote** command displays summary remote IPv6 EID-prefix information. Summary information is displayed when the keyword **detail** is not used. The display shows the EID prefix, associated locator status bits, and total encapsulated packets and bytes for each remote IPv6 EID prefix.

```
Router# show lisp instance-id [0-16777200] ipv6 forwarding eid remote

Prefix          Fwd action  Locator status bits
::/0           signal     0x00000000
  packets/bytes 0/0
2001:DB8:AB::/48 encap      0x00000001
  packets/bytes 25/2150
```

The following sample output from the **show lisp instance-id [0-16777200] forwarding eid remote detail** command displays detailed remote IPv6 EID-prefix information by adding the **detail** keyword. The display shows the EID-prefix, associated locator status bits, and total encapsulated packets/bytes for each remote IPv6 EID prefix.

```
Router# show lisp instance-id [0-16777200] ipv6 forwarding eid remote detail

Prefix          Fwd action  Locator status bits
::/0            signal      0x00000000
  packets/bytes  0/0
  path list 0729CE78, flags 0x49, 3 locks, per-destination
  ifnums:
    LISP0(14)
  1 path
    path 0729D4E0, path list 0729CE78, share 1/1, type attached prefix, for IPv6
    attached to LISP0, adjacency glean for LISP0
  1 output chain
  chain[0]: glean for LISP0
2001:DB8:AB::/48  encap        0x00000001
  packets/bytes  25/2150
  path list 06BFA050, flags 0x49, 3 locks, per-destination
  ifnums:
    LISP0(14): 10.0.0.6
  1 path
    path 06E8C5B0, path list 06BFA050, share 100/100, type attached nexthop, for IPv6
    nexthop 10.0.0.6 LISP0, adjacency IPV6 midchain out of LISP0, addr 10.0.0.6 07374688
  1 output chain
Prefix          Fwd action  Locator status bits
chain[0]: IPV6 midchain out of LISP0, addr 10.0.0.6 07374688 IP adj out of Ethernet0/0,
addr 10.0.0.2 0620D8A8
```

The following sample output from the **show lisp instance-id [0-16777200] forwarding state** command displays detailed information about the state of the LISP process forwarding state. (Both IPv4 and IPv6 information is presented).

```
Router# show lisp instance-id [0-16777200] ipv6 forwarding state

LISP forwarding state for EID table IPv4:Default
EID VRF          Default (0x0)
  IPv4
    Configured roles  ITR|ETR
    Active roles      ITR|ETR
    EID table         IPv4:Default
    ALT table         <null>
    Locator status bits 0x00000001
  IPv6
    Configured roles  ITR|ETR
    Active roles      ITR|ETR
    EID table         IPv6:Default
    ALT table         <null>
    Locator status bits 0x00000001
  RLOC transport VRF  Default (0x0)
    IPv4 RLOC table   IPv4:Default
    IPv6 RLOC table   IPv6:Default
  LISP virtual interface  LISP0
```



**Related Commands**

<b>Command</b>	<b>Description</b>
<b>database-mapping</b>	Configures an IPv6 EID-to-RLOC mapping relationship and its associated traffic policy.
<b>ipv6 lisp etr accept-map-request-mapping</b>	Configures an ETR to cache IPv6 mapping data contained in a map-request message.
<b>show ipv6 lisp map-cache</b>	Displays the current dynamic and static IPv6 EID-to-RLOC map-cache entries.

# show ipv6 lisp instance-id



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp instance-id [0-16777200]**.

To display the negative prefix hole in the LISP ALT for an EID within a specified instance-id, use the **show ipv6 lisp instance-id** command in privileged EXEC mode.

**show ipv6 lisp instance-id iid alt negative-prefix EID-prefix**

## Syntax Description

<i>iid</i>	EID instance-id.
<i>EID-prefix</i>	IPv4 EID address covered by negative ALT prefix.

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
15.1(1)XB3	This command was introduced.
2.5.1XC	This command was integrated into Cisco IOS XE Release 2.5.1XC.

## Usage Guidelines

This command is only used on LISP Map-Server (MS) devices to display the negative prefix hole in the LISP ALT for an EID within a specified instance-id.

## Examples

The following sample output from the show ip lisp instance-id command for the instance-id 123 and EID 2001:db8:c::1.

```
Router# show ipv6 lisp instance-id 123 alt negative-prefix 2001:db8:c::1
Negative mapping system prefix 2001:DB8:C::/46
Router#
```

## Related Commands

Command	Description
<b>eid-prefix (LISP site)</b>	Configures the EID-prefix associated with a LISP site on a Map-Server as part of the LISP Site configuration process.

## show lisp instance-id ipv6 alt

To display the negative prefix hole in the LISP ALT for an EID within a specified instance-id, use the **show lispinstance-idalt** command in privileged EXEC mode.

```
show lisp instance-id alt
```

**Command Modes** Privileged EXEC (#)

Command History	Release	Modification
	Cisco IOS XE Dublin 17.11.1a	This command was introduced.

**Usage Guidelines** This command is only used on LISP Map-Server (MS) devices to display the negative prefix hole in the LISP ALT for an EID within a specified instance-id.

### Examples

The following sample output from the show ip lisp instance-id command for the instance-id 123 and EID 2001:db8:c::1.

```
Router# ow lisp instance-id 123 ipv6 alt negative-prefix 172.16.0.1
Negative mapping system prefix 2001:DB8:C::/46
Router#
```

Related Commands	Command	Description
	<b>eid-prefix (LISP site)</b>	Configures the EID-prefix associated with a LISP site on a Map-Server as part of the LISP Site configuration process.

# show ipv6 lisp locator-table



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp locator table**.

To display Locator/ID Separation Protocol (LISP) IPv6 configurations associated with a specific locator table, use the **show ipv6 lisp locator-table** command in privileged EXEC mode.

**show ipv6 lisp locator-table** {default | vrf *vrf-name*}

## Syntax Description

<b>default</b>	Displays IPv6 LISP information and configuration status related to the default table.
<b>vrf</b> <i>vrf-name</i>	Displays IPv6 LISP information and configuration status related to the specified VRF name.

## Command Modes

Privileged EXEC

## Command History

Release	Modification
15.1(1)XB6	This command was introduced.
15.1(4)M	This command was integrated into Cisco IOS Release 15.1(4)M.
Cisco IOS XE Release 3.3S	This command was integrated into Cisco IOS XE Release 3.3S.

## Usage Guidelines

The **locator-table** command creates an association between a LISP instantiation and a virtual routing and forwarding (VRF) table through which the routing locator address space is reachable. The **show ipv6 lisp locator-table** command is used to display the IPv6 LISP configuration status for a specific locator table. A locator table can be the default, meaning the global routing table, or a specific VRF.

## Examples

The following is sample output from the **show ipv6 lisp locator-table** command for the VRF named Cust-1:

```
Router# show ipv6 lisp locator-table Cust-1

Information applicable to all EID instances:
Router-lisp ID:                1
Locator table:                 vrf Cust-1
Ingress Tunnel Router (ITR):   disabled
Egress Tunnel Router (ETR):    disabled
Proxy-ITR Router (PITR):      enabled RLOCs: 2001:db8:1:1::1
Proxy-ETR Router (PETR):      enabled
Map Server (MS):              disabled
Map Resolver (MR):            disabled
Delegated Database Tree (DDT): disabled
ITR Map-Resolver(s):          10.100.1.2
ITR Solicit Map Request (SMR): accept and process
  Max SMRs per map-cache entry: 8 more specifics
  Multiple SMR suppression time: 20 secs
```

```
ETR accept mapping data:      disabled, verify disabled
ETR map-cache TTL:           1d00h
Locator Status Algorithms:
  RLOC-probe algorithm:      disabled
  LSB reports:               process
Map-cache limit:             1000
Map-cache activity check period: 60 secs
Persistent map-cache:        disabled
Router#
```

**Related Commands**

Command	Description
<b>locator-table</b>	Configure the association of a VRF table through which the routing locator address space is reachable to a router LISP instantiation.

# show ipv6 lisp map-cache



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp instance-id [0-16777200] ipv6 map-cache**.

To display the current dynamic and static IPv6 endpoint identifier-to-routing locator (EID-to-RLOC) map-cache entries, use the **show ipv6 lisp map-cache** command in privileged EXEC mode.

**show ipv6 lisp map-cache** [*destination-EID* | *destination-EID-prefix/prefix-length* | **detail**]

## Syntax Description

<i>destination-EID</i>	(Optional) Destination EID for which to display mapping information.
<i>destination-EID-prefix/prefix-length</i>	(Optional) Destination EID prefix for which to display mapping information.
<b>detail</b>	(Optional) Displays detailed EID-to-RLOC cache mapping information.

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
15.1(1)XB1	This command was introduced.
Cisco IOS XE Release 2.5.1XA	This command was integrated into Cisco IOS XE Release 2.5.1XA.
Cisco IOS XE Release 3.3.0S	This command was integrated into Cisco IOS XE Release 3.3.0S.
15.1(4)M	This command was integrated into Cisco IOS Release 15.1(4)M.

## Usage Guidelines

This command is used to display the current dynamic and static IPv6 EID-to-RLOC map-cache entries. When no IPv6 EID or IPv6 EID-prefix is specified, summary information is listed for all current dynamic and static IPv6 EID-to-RLOC map-cache entries. When an IPv6 EID or IPv6 EID prefix is included, information is listed for the longest-match lookup in the cache. When the **detail** option is used, detailed (rather than summary) information related to all current dynamic and static IPv4 or IPv6 EID-to-RLOC map-cache entries is displayed.

## Examples

The following sample output from the **show ipv6 lisp map-cache** command (without the use of an IPv6 EID or IPv6 EID-prefix) displays a summary list of current dynamic and static IPv6 EID-to-RLOC map-cache entries. The display shows the IPv6 EID prefix and associated information:

```
Router# show ipv6 lisp map-cache

LISP IPv6 Mapping Cache, 2 entries

::/0, uptime: 00:00:26, expires: never, via static
```

```

Negative cache entry, action: send-map-request
2001:DB8:AB::/48, uptime: 00:00:04, expires: 23:59:53, via map-reply, complete
Locator  Uptime   State   Pri/Wgt
10.0.0.6 00:00:04 up      1/100
Router#

```

The following sample output from the **show ipv6 lisp map-cache detail** command displays a detailed list of current dynamic and static IPv4 EID-to-RLOC map-cache entries:

```

Router# show ipv6 lisp map-cache detail

LISP IPv6 Mapping Cache, 2 entries

::/0, uptime: 00:00:52, expires: never, via static
State: send-map-request, last modified: 00:00:52, map-source: local
Idle, Packets out: 0
Negative cache entry, action: send-map-request
2001:DB8:AB::/48, uptime: 00:00:30, expires: 23:59:27, via map-reply, complete
State: complete, last modified: 00:00:30, map-source: 10.0.0.6
Active, Packets out: 0
Locator  Uptime   State   Pri/Wgt
10.0.0.6 00:00:30 up      1/100
Last up-down state change:      never, state change count: 0
Last priority / weight change:  never/never
RLOC-probing loc-status algorithm:
Last RLOC-probe sent:          never

```

The following sample output from the **show ipv6 lisp map-cache** command with a specific IPv6 EID prefix displays detailed information associated with that IPv6 EID prefix entry.

```

Router# show ipv6 lisp map-cache 2001:DB8:AB::/48

LISP IPv6 Mapping Cache, 2 entries

2001:DB8:AB::/48, uptime: 00:01:02, expires: 23:58:54, via map-reply, complete
State: complete, last modified: 00:01:02, map-source: 10.0.0.6
Active, Packets out: 0
Locator  Uptime   State   Pri/Wgt
10.0.0.6 00:01:02 up      1/100
Last up-down state change:      never, state change count: 0
Last priority / weight change:  never/never
RLOC-probing loc-status algorithm:
Last RLOC-probe sent:          never

```

#### Related Commands

Command	Description
<b>show ipv6 lisp forwarding</b>	Displays LISP local or remote IPv6 EID-prefix information.

## show lisp instance-id ipv6 map-cache

To display the current dynamic and static IPv6 endpoint identifier-to-routing locator (EID-to-RLOC) map-cache entries, use the **show lisp instance-id [0-16777200]ipv6map-cache** command in privileged EXEC mode.

**show lisp instance-id [0-16777200] ipv6 map-cache** [{ *destination-EID* | *destination-EID-prefix* / *prefix-length* | **detail** }]

Syntax Description		
	<i>destination-EID</i>	(Optional) Destination EID for which to display mapping information.
	<i>destination-EID-prefix/prefix-length</i>	(Optional) Destination EID prefix for which to display mapping information.
	<b>detail</b>	(Optional) Displays detailed EID-to-RLOC cache mapping information.

**Command Modes** Privileged EXEC (#)

Command History	Release	Modification
	Cisco IOS XE Dublin 17.11.1a	This command was introduced.

**Usage Guidelines** This command is used to display the current dynamic and static IPv6 EID-to-RLOC map-cache entries. When no IPv6 EID or IPv6 EID-prefix is specified, summary information is listed for all current dynamic and static IPv6 EID-to-RLOC map-cache entries. When an IPv6 EID or IPv6 EID prefix is included, information is listed for the longest-match lookup in the cache. When the **detail** option is used, detailed (rather than summary) information related to all current dynamic and static IPv4 or IPv6 EID-to-RLOC map-cache entries is displayed.

### Examples

The following sample output from the **show lisp instance-id [0-16777200]ipv6 map-cache** command (without the use of an IPv6 EID or IPv6 EID-prefix) displays a summary list of current dynamic and static IPv6 EID-to-RLOC map-cache entries. The display shows the IPv6 EID prefix and associated information:

```
Router# show ipv6 lisp instance-id [0-16777200] map-cache

LISP IPv6 Mapping Cache, 2 entries

::/0, uptime: 00:00:26, expires: never, via static
  Negative cache entry, action: send-map-request
2001:DB8:AB::/48, uptime: 00:00:04, expires: 23:59:53, via map-reply, complete
  Locator    Uptime    State     Pri/Wgt
  10.0.0.6   00:00:04  up        1/100
Router#
```

The following sample output from the **show lisp instance-id [0-16777200]ipv6map-cache detail** command displays a detailed list of current dynamic and static IPv4 EID-to-RLOC map-cache entries:

```
Router# show lisp instance-id [0-16777200] ipv6 map-cache detail

LISP IPv6 Mapping Cache, 2 entries
```



```

::/0, uptime: 00:00:52, expires: never, via static
  State: send-map-request, last modified: 00:00:52, map-source: local
  Idle, Packets out: 0
  Negative cache entry, action: send-map-request
2001:DB8:AB::/48, uptime: 00:00:30, expires: 23:59:27, via map-reply, complete
  State: complete, last modified: 00:00:30, map-source: 10.0.0.6
  Active, Packets out: 0
  Locator  Uptime  State  Pri/Wgt
  10.0.0.6  00:00:30  up     1/100
    Last up-down state change:      never, state change count: 0
    Last priority / weight change:   never/never
    RLOC-probing loc-status algorithm:
    Last RLOC-probe sent:           never

```

The following sample output from the **showlispinstance-id [0-16777200]ipv6map-cache** command with a specific IPv6 EID prefix displays detailed information associated with that IPv6 EID prefix entry.

```

Router# show lisp instance-id [0-16777200] ipv6 map-cache 2001:DB8:AB::/48

LISP IPv6 Mapping Cache, 2 entries

2001:DB8:AB::/48, uptime: 00:01:02, expires: 23:58:54, via map-reply, complete
  State: complete, last modified: 00:01:02, map-source: 10.0.0.6
  Active, Packets out: 0
  Locator  Uptime  State  Pri/Wgt
  10.0.0.6  00:01:02  up     1/100
    Last up-down state change:      never, state change count: 0
    Last priority / weight change:   never/never
    RLOC-probing loc-status algorithm:
    Last RLOC-probe sent:           never

```

#### Related Commands

Command	Description
<b>show ipv6 lisp forwarding</b>	Displays LISP local or remote IPv6 EID-prefix information.

# show ipv6 lisp route-import database



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp instance-id [0-16777200] ipv6 route-import database**.

To display the current IPv6 Routing Information Base (RIB) routes imported into Locator ID Separation Protocol (LISP) to define local endpoint identifier (EID) database entries, use the **show ipv6 lisp route-import database** command in privileged EXEC mode.

```
show ipv6 lisp [router-lisp-id] [instance-id iid] route-import database [ipv6-address | ipv6-prefix
| eid-table { vrf eid-table-vrf-name | default } ]
```

## Syntax Description

<i>router-lisp-id</i>	(Optional) Router LISP ID. Range: 0 to 65520.
<b>instance-id</b> <i>iid</i>	(Optional) Limits the output of the command to the referenced instance ID. Range: 0 to 16777214
<i>ipv6-address</i>	(Optional) IPv6 address to longest match against imported routes.
<i>ipv6-prefix</i>	(Optional) IPv6 imported route prefix.
<b>eid-table</b>	(Optional) Limits the output of the command to the referenced EID table.
<b>vrf</b> <i>eid-table-vrf-name</i>	VRF name.
<b>default</b>	Default VRF.

## Command Modes

Privileged EXEC (#)

## Command History

### Release Modification

15.4(2)T This command was introduced.

3.12.0S This command was integrated into Cisco IOS XE Release 3.12.0S.

## Usage Guidelines

When the optional *lisp-instantiation-number* argument is used, the **show ip lisp route-import database** command displays the IPv6 LISP configuration status for the specified router LISP instantiation. When used without the optional *lisp-instantiation-number* argument, the command displays the IPv6 LISP configuration status for the local device for the default router LISP instantiation.

It is mandatory to use the *iid* argument with the **instance-id** keyword. When the optional **instance-id** keyword is used with the *iid* argument, the **show ip lisp route-import database** command displays the IPv6 LISP configuration status for the local device for the specified LISP instance ID associated with a VRF. When used without the optional **instance-id** keyword, the command displays the IPv6 LISP configuration status for the local device for all LISP configurations present on the device.

When used with the optional *ipv6-address* or *ipv6-prefix* arguments, the **show ip lisp route-import database** command displays the IPv6 LISP configuration status for the local device for IPv6 address to longest match against imported routes or IPv6 imported route prefix respectively. When used without either of the optional *ipv6-address* or *ipv6-prefix* arguments, the command displays the IPv6 LISP configuration status for the local device for all IPv6 addresses or prefixes that are configured on the device.

### Example

The following example shows how to display the current IPv6 RIB routes imported into LISP to define local EID database entries using the **show ipv6 lisp route-import database** command:

```
Device# show ipv6 lisp route-import database

LISP IPv6 imported routes for EID-table default (IID 0)
Config: 1, Entries: 4 (limit 1000)
Prefix                Uptime      Source  Map-cache  State
2001:db8:10:1::/64    00:56:26   ospf 10  installed
2001:db8:ab:cd:1::/80 00:17:52   ospf 10  installed
2001:db8:ab:cd:2::/80 00:17:52   ospf 10  installed
2001:db8:ab:cd:3::/80 00:17:52   ospf 10  installed
```

### Related Commands

Command	Description
<b>show ip lisp route-import database</b>	Displays the current IPv4 RIB routes imported into LISP to define local EID database entries.
<b>show ip lisp route-import map-cache</b>	Displays the current IPv4 RIB routes imported into LISP to define EID address space in map-cache.
<b>show ipv6 lisp route-import map-cache</b>	Displays the current IPv6 RIB routes imported into LISP to define EID address space in map-cache.

## show lisp instance-id ipv6 route-import database

To display the current IPv6 Routing Information Base (RIB) routes imported into Locator ID Separation Protocol (LISP) to define local endpoint identifier (EID) database entries, use the **show lisp instance-id [0-16777200] ipv6 route-import database** command in privileged EXEC mode.

```
show lisp instance-id [0-16777200] [ router-lisp-id ] [ instance-id iid ] ipv6 route-import
database [ ipv6-address | ipv6-prefix | eid-table { vrf eid-table-vrf-name | default
} ]
```

### Syntax Description

<i>router-lisp-id</i>	(Optional) Router LISP ID. Range: 0 to 65520.
<b>instance-id</b> <i>iid</i>	(Optional) Limits the output of the command to the referenced instance ID. Range: 0 to 16777214
<i>ipv6-address</i>	(Optional) IPv6 address to longest match against imported routes.
<i>ipv6-prefix</i>	(Optional) IPv6 imported route prefix.
<b>eid-table</b>	(Optional) Limits the output of the command to the referenced EID table.
<b>vrf</b> <i>eid-table-vrf-name</i>	VRF name.
<b>default</b>	Default VRF.

### Command Modes

Privileged EXEC (#)

### Command History

Release	Modification
Cisco IOS XE Dublin 17.11.1a	This command was introduced.

### Usage Guidelines

When the optional *lisp-instantiation-number* argument is used, the **show lisp instance-id [0-16777200] ipv6 route-import database** command displays the IPv6 LISP configuration status for the specified router LISP instantiation. When used without the optional *lisp-instantiation-number* argument, the command displays the IPv6 LISP configuration status for the local device for the default router LISP instantiation.

It is mandatory to use the *iid* argument with the **instance-id** keyword. When the optional **instance-id** keyword is used with the *iid* argument, the **show lisp instance-id [0-16777200] ipv6 route-import database** command displays the IPv6 LISP configuration status for the local device for the specified LISP instance ID associated with a VRF. When used without the optional **instance-id** keyword, the command displays the IPv6 LISP configuration status for the local device for all LISP configurations present on the device.

When used with the optional *ipv6-address* or *ipv6-prefix* arguments, the **show lisp instance-id [0-16777200] ipv6 route-import database** command displays the IPv6 LISP configuration status for the local device for IPv6 address to longest match against imported routes or IPv6 imported route prefix respectively. When used without either of the optional *ipv6-address* or *ipv6-prefix* arguments, the command displays the IPv6 LISP configuration status for the local device for all IPv6 addresses or prefixes that are configured on the device.

**Example**

The following example shows how to display the current IPv6 RIB routes imported into LISP to define local EID database entries using the **show lisp instance-id [0-16777200] ipv6 route-import database** command:

```
Device# show lisp instance-id [0-16777200] ipv6 route-import database

LISP IPv6 imported routes for EID-table default (IID 0)
Config: 1, Entries: 4 (limit 1000)
Prefix                Uptime      Source  Map-cache  State
2001:db8:10:1::/64    00:56:26   ospf 10  installed
2001:db8:ab:cd:1::/80 00:17:52   ospf 10  installed
2001:db8:ab:cd:2::/80 00:17:52   ospf 10  installed
2001:db8:ab:cd:3::/80 00:17:52   ospf 10  installed
```

**Related Commands**

Command	Description
<b>show ip lisp route-import database</b>	Displays the current IPv4 RIB routes imported into LISP to define local EID database entries.
<b>show ip lisp route-import map-cache</b>	Displays the current IPv4 RIB routes imported into LISP to define EID address space in map-cache.
<b>show ipv6 lisp route-import map-cache</b>	Displays the current IPv6 RIB routes imported into LISP to define EID address space in map-cache.

# show ipv6 lisp route-import map-cache



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp instance-id [0-16777200] ipv6 route-import map-cache**.

To display the current IPv6 Routing Information Base (RIB) routes imported into Locator ID Separation Protocol (LISP) to define endpoint identifier (EID) address space in map cache, use the **show ipv6 lisp route-import map-cache** command in privileged EXEC mode.

```
show ipv6 lisp [router-lisp-id] [instance-id iid] route-import map-cache [ipv6-address |
ipv6-prefix | eid-table { vrf eid-table-vrf-name | default } ]
```

## Syntax Description

<i>router-lisp-id</i>	(Optional) Router LISP ID. Range: 0 to 65520.
<b>instance-id</b> <i>i-id</i>	(Optional) Limits the output of the command to the referenced instance ID. Range: 0 to 16777214
<i>ipv6-address</i>	(Optional) IPv6 address to longest match against imported routes.
<i>ipv6-prefix</i>	(Optional) IPv6 imported route prefix.
<b>eid-table</b>	(Optional) Limits the output of the command to the referenced EID table.
<b>vrf</b> <i>eid-table-vrf-name</i>	VRF name.
<b>default</b>	Default VRF.

## Command Modes

Privileged EXEC (#)

## Command History

### Release Modification

15.4(2)T This command was introduced.

3.12.0S This command was integrated into Cisco IOS XE Release 3.12.0S.

## Usage Guidelines

When the optional *lisp-instantiation-number* argument is used, the **show ipv6 lisp route-import map-cache** command displays the IPv6 LISP configuration status for the specified router LISP instantiation. When used without the optional *lisp-instantiation-number* argument, the command displays the IPv6 LISP configuration status for the local device for the default router LISP instantiation.

It is mandatory to use the *iid* argument with the **instance-id** keyword. When the optional **instance-id** keyword is used with the *iid* argument, the **show ipv6 lisp route-import map-cache** command displays the IPv6 LISP configuration status for the local device for the specified LISP instance ID associated with a VRF. When used without the optional **instance-id** keyword, the command displays the IPv6 LISP configuration status for the local device for all LISP configurations present on the device.

When used with the optional *ipv6-address* or *ipv6-prefix* arguments, the **show ipv6 lisp route-import map-cache** command displays the IPv6 LISP configuration status for the local device for IPv6 address to longest match against imported routes or IPv6 imported route prefix respectively. When used without either of the optional *ipv6-address* or *ipv6-prefix* arguments, the command displays the IPv6 LISP configuration status for the local device for all IPv6 addresses or prefixes that are configured on the device.

### Example

The following example shows how to display the current IPv6 RIB routes imported into LISP to define EID address space in map-cache using the **show ipv6 lisp route-import map-cache** command:

```
Device# show ipv6 lisp route-import map-cache

LISP IPv6 imported routes for EID-table default (IID 0)
Config: 1, Entries: 4 (limit 1000)
Prefix                Uptime      Source      Map-cache  State
2001:db8:ab:cd::/64   00:19:50   bgp 64496   installed
2001:db8:cd::/48     00:25:32   bgp 64496   installed
2001:db8:ce::/48     00:27:11   bgp 64496   installed
2001:db8:cf::/48     00:12:12   bgp 64496   installed
```

### Related Commands

Command	Description
<b>show ip lisp route-import database</b>	Displays the current IPv4 RIB routes imported into LISP to define local EID database entries.
<b>show ip lisp route-import map-cache</b>	Displays the current IPv4 RIB routes imported into LISP to define EID address space in map-cache.
<b>show ipv6 lisp route-import database</b>	Displays the current IPv6 RIB routes imported into LISP to define local EID database entries.

## show lisp instance-id ipv6 route-import map-cache

To display the current IPv6 Routing Information Base (RIB) routes imported into Locator ID Separation Protocol (LISP) to define endpoint identifier (EID) address space in map cache, use the **show lisp instance-id [0-16777200] ipv6 route-import map-cache** command in privileged EXEC mode.

```
show lisp [ router-lisp-id ] [ instance-id iid ] ipv6 route-import map-cache [ ipv6-address
| ipv6-prefix | eid-table { vrf eid-table-vrf-name | default } ]
```

Syntax Description		
<i>router-lisp-id</i>	(Optional) Router LISP ID. Range: 0 to 65520.	
<b>instance-id</b> <i>i-id</i>	(Optional) Limits the output of the command to the referenced instance ID. Range: 0 to 16777214	
<i>ipv6-address</i>	(Optional) IPv6 address to longest match against imported routes.	
<i>ipv6-prefix</i>	(Optional) IPv6 imported route prefix.	
<b>eid-table</b>	(Optional) Limits the output of the command to the referenced EID table.	
<b>vrf</b> <i>eid-table-vrf-name</i>	VRF name.	
<b>default</b>	Default VRF.	

**Command Modes** Privileged EXEC (#)

Command History	Release	Modification
	Cisco IOS XE Dublin 17.11.1a	This command was introduced.

\[]÷

**Usage Guidelines** When the optional *lisp-instantiation-number* argument is used, the **show lisp instance-id [0-16777200]ipv6route-import map-cache** command displays the IPv6 LISP configuration status for the specified router LISP instantiation.

When used without the optional *lisp-instantiation-number* argument, the command displays the IPv6 LISP configuration status for the local device for the default router LISP instantiation.

It is mandatory to use the *iid* argument with the **instance-id** keyword. When the optional **instance-id** keyword is used with the *iid* argument, the **show instance-id [0-16777200] ipv6lisp route-import map-cache** command displays the IPv6 LISP configuration status for the local device for the specified LISP instance ID associated with a VRF. When used without the optional **instance-id** keyword, the command displays the IPv6 LISP configuration status for the local device for all LISP configurations present on the device.

When used with the optional *ipv6-address* or *ipv6-prefix* arguments, the **show lispinstance-id [0-16777200] ipv6 route-import map-cache** command displays the IPv6 LISP configuration status for the local device for IPv6 address to longest match against imported routes or IPv6 imported route prefix respectively. When used without either of the optional *ipv6-address* or *ipv6-prefix* arguments, the command displays the IPv6 LISP configuration status for the local device for all IPv6 addresses or prefixes that are configured on the device.



### Example

The following example shows how to display the current IPv6 RIB routes imported into LISP to define EID address space in map-cache using the **show lispinstance-id [0-16777200]ipv6 route-import map-cache** command:

```
Device# show lisp instance-id ipv6 route-import map-cache

LISP IPv6 imported routes for EID-table default (IID 0)
Config: 1, Entries: 4 (limit 1000)
Prefix          Uptime          Source          Map-cache      State
2001:db8:ab:cd::/64      00:19:50      bgp 64496      installed
2001:db8:cd::/48        00:25:32      bgp 64496      installed
2001:db8:ce::/48        00:27:11      bgp 64496      installed
2001:db8:cf::/48        00:12:12      bgp 64496      installed
```

### Related Commands

Command	Description
<b>show ip lisp route-import database</b>	Displays the current IPv4 RIB routes imported into LISP to define local EID database entries.
<b>show ip lisp route-import map-cache</b>	Displays the current IPv4 RIB routes imported into LISP to define EID address space in map-cache.
<b>show ipv6 lisp route-import database</b>	Displays the current IPv6 RIB routes imported into LISP to define local EID database entries.

# show ipv6 lisp statistics



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp instance-id [0-16777200] ipv6 statistics**.

To display Locator/ID Separation Protocol (LISP) IPv6 address-family statistics, use the **show ipv6 lisp statistics** command in privileged EXEC mode.

## show ipv6 lisp statistics

**Syntax Description** This command has no arguments or keywords.

**Command Modes** Privileged EXEC (#)

### Command History

Release	Modification
15.1(1)XB1	This command was introduced.
Cisco IOS XE Release 2.5.1XA	This command was integrated into Cisco IOS XE Release 2.5.1XA.
Cisco IOS XE Release 3.3.0S	This command was integrated into Cisco IOS XE Release 3.3.0S.
15.1(4)M	This command was integrated into Cisco IOS Release 15.1(4)M.

**Usage Guidelines** This command is used to display IPv6 LISP statistics related to packet encapsulations, de-encapsulations, map requests, map replies, map registers, and other LISP-related packets.

### Examples

The following sample output from the **show ipv6 lisp statistics** command displays the current LISP IPv6 address family statistics. The output varies, depending on the LISP features configured and the state of various LISP components.

```
Router# show ipv6 lisp statistics

LISP Statistics - last cleared: 00:56:49
Control Packets:
  Map-Requests in/out:                0/15
  Encapsulated Map-Requests in/out:   0/15
  RLOC-probe Map-Requests in/out:     0/0
  Map-Reply records in/out:           4/0
  Authoritative records in/out:       4/0
  Non-authoritative records in:       0
  Negative records in:                0
  RLOC-probe records in/out:          1/0
  Map-Registers out:                  114
Errors:
  Map-Request format errors:          0
  Map-Reply format errors:            0
  Map-Reply spoof alerts:             0
```

```
Mapping record TTL alerts:          0
Cache Related:
  Cache entries created/deleted:    8/7
  Number of EID-prefixes in map-cache: 3
  Number of negative entries in map-cache: 2
  Total number of RLOCs in map-cache: 2
  Average RLOCs per EID-prefix:     2
Forwarding:
  Number of data signals processed:  0 (+ dropped 0)
  Number of reachability reports:    0 (+ dropped 0)
```

**Related Commands**

Command	Description
<b>show ipv6 lisp</b>	Displays the IPv6 LISP configuration status for the local device.

# show lisp ipv6 statistics

To display Locator/ID Separation Protocol (LISP) IPv6 address-family statistics, use the **show lisp ipv6 statistics** command in privileged EXEC mode.

**show lisp ipv6 statistics**

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
Cisco IOS XE Dublin 17.11.1a	This command was introduced.

## Usage Guidelines

This command is used to display IPv6 LISP statistics related to packet encapsulations, de-encapsulations, map requests, map replies, map registers, and other LISP-related packets.

## Examples

The following sample output from the **show lisp ipv6 statistics** command displays the current LISP IPv6 address family statistics. The output varies, depending on the LISP features configured and the state of various LISP components.

```
Router# Router# show ipv6 lisp statistics
LISP Statistics - last cleared: 00:56:49
Control Packets:
Map-Requests in/out: 0/15
Encapsulated Map-Requests in/out: 0/15
RLOC-probe Map-Requests in/out: 0/0
Map-Reply records in/out: 4/0
Authoritative records in/out: 4/0
Non-authoritative records in: 0
Negative records in: 0
RLOC-probe records in/out: 1/0
Map-Registers out: 114
Errors:
Map-Request format errors: 0
Map-Reply format errors: 0
Map-Reply spoof alerts: 0
Mapping record TTL alerts: 0
Cache Related:
Cache entries created/deleted: 8/7
Number of EID-prefixes in map-cache: 3
Number of negative entries in map-cache: 2
Total number of RLOCs in map-cache: 2
Average RLOCs per EID-prefix: 2
Forwarding:
Number of data signals processed: 0 (+ dropped 0)
Number of reachability reports: 0 (+ dropped 0)
```

## Related Commands

Command	Description
<b>show ipv6 lisp</b>	Displays the IPv6 LISP configuration status for the local device.

# show lisp

To display summary information related to the Locator/ID Separation Protocol (LISP) configuration, use the **show lisp** command in privileged EXEC mode.

```
show lisp [{router-lisp-id}]
```

## Syntax Description

<i>router-lisp-id</i>	(Optional) Router LISP instantiation ID. Valid values are 0 to 15.
-----------------------	--

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
15.1(1)XB6	This command was introduced.
15.1(4)M	This command was integrated into Cisco IOS Release 15.1(4)M and modified to include the <b>locator-table</b> keyword.
Cisco IOS XE Release 3.3S	This command was integrated into Cisco IOS XE Release 3.3S and modified to include the <b>locator-table</b> keyword.

## Usage Guidelines

When used without the optional router LISP ID value, the **show lisp** command displays summary information about the default router LISP process, including any associated locator table or EID instance IDs. When the optional *router-lisp-id* argument is used, the **show lisp** command displays the summary locator table or EID instance IDs related to the specified router LISP instantiation.

## Examples

The following is sample output from the **show lisp** command:

```
Router# show lisp

Router-lisp ID:      0
Locator table:      default
EID instance count: 1
Router#
```

The following is sample output from the **show lisp** command when using the optional router LISP ID (and a configuration exists for this router LISP instantiation):

```
Router# show lisp 1

Router-lisp ID:      1
Locator table:      vrf Cust-1
EID instance count: 1
Router#
```

## Related Commands

Command	Description
<b>router lisp</b>	Configures a LISP instantiation on the device.

## show lisp ddt

To display the configured DDT root(s) and/or DDT delegation nodes on a router enabled for LISP DDT, use the **show lisp ddt** command in privileged EXEC mode.

**show lisp ddt** [{**negative-prefix** | **referral-cache** | {*eid-addressid*} | **queue**}]

### Syntax Description

<b>negative-prefix</b>	(Optional) Displays the DDT node delegation hole.
<b>referral-cache</b>	(Optional) Displays the DDT referral cache contents.
<i>eid-address</i>	(Optional) IPv4/IPv6 EID address or prefix.
<i>iid</i>	(Optional) EID instance ID.
<b>queue</b>	(Optional) Displays the DDT request queue.

### Command Modes

Privileged EXEC (#)

### Command History

Release	Modification
15.3(1)T	This command was introduced.
Cisco IOS XE Release 3.8S	This command was integrated into Cisco IOS XE Release 3.8S.

### Usage Guidelines

Use this command to display the configured DDT root(s) and/or DDT delegation nodes on a device that is enabled for LISP DDT node.

### Example

The following example shows the output of the **show lisp ddt** command for a LISP DDT node configured as a map resolver that refers to three LISP DDT root nodes with locators (10.1.1.1, 10.2.1.1, and 10.3.1.1) and configured as a map server for the EID prefixes 172.16.0.0/16 and 2001:db8:eeee::/48 in the default (0) instance ID for its own locator (10.1.10.10) and a peer map server locator (10.2.10.10).

```
Device> enable
Device# show lisp ddt

LISP-DDT Configuration in VRF "default"
  DDT IP Map-Resolver configured
  DDT IPv6 Map-Resolver configured
  DDT IP Map-Server configured
  DDT IPv6 Map-Server configured
Configured DDT roots: 10.1.1.1 10.2.1.1 10.3.1.1
Configured DDT delegated nodes/map-servers:
  [0] 172.16.0.0/16 -> 10.1.10.10, p/w: 0/0, map-server-peer
  [0] 172.16.0.0/16 -> 10.2.10.10, p/w: 0/0, map-server-peer
  [0] 2001:db8:eeee::/48 -> 10.1.10.10, p/w: 0/0, map-server-peer
  [0] 2001:db8:eeee::/48 -> 10.2.10.10, p/w: 0/0, map-server-peer

Configured authoritative EID-prefixes:
```

```
[0] 172.16.0.0/16  
[0] 2001:db8:eeee::/48
```

**Related Commands**

<b>Command</b>	<b>Description</b>
<b>clear lisp ddt</b>	Clears the DDT referral cache stored on a DDT-enabled map resolver.
<b>ddt</b>	Configures a device to enable LISP DDT functionality.

## show lisp decapsulation filter

To display source Routing Locator (RLOC) addresses for specified parameters and the corresponding RLOC address configuration method, use the **show lisp decapsulation filter** command in privileged EXEC mode.

**show lisp decapsulation filter** [*IPv4-rloc-address* | *IPv6-rloc-address*] [**eid-table** *eid-table-vrf* | **instance-id** *iid*]

Syntax Description		
<i>IPv4-rloc-address</i>	(Optional) Source RLOC address. If you want to know how a specific IPv4 RLOC address was configured, use this option.	
<i>IPv6-rloc-address</i>	(Optional) Source RLOC address. If you want to know how a specific IPv6 RLOC address was configured, use this option.	
<b>eid-table</b> <i>eid-table-vrf</i>	(Optional) Specifies the EID table and the associated VRF. Source RLOC addresses corresponding to the VRF will be displayed.	
<b>instance-id</b> <i>iid</i>	(Optional) Specifies the instance ID. Source RLOC addresses corresponding to the specified instance ID will be displayed.	

**Command Modes** Privileged EXEC (#)

Command History	Release	Modification
	15.5(1)T	This command was introduced.
	Cisco IOS XE Release 3.14S	This command was integrated into Cisco IOS XE Release 3.14S.

### Usage Guidelines

#### Examples

The following sample output from the **show lisp decapsulation filter** command displays source RLOC address configuration details for a specific EID Instance ID:

```
Device# show lisp decapsulation filter instance-id 0

LISP decapsulation filter for EID-table default (IID 0), 3 entries

Source RLOC      Added by
10.0.0.1         Config
10.0.0.5         209.165.200.230 209.165.200.232
10.0.0.6         Config 209.165.200.230
```

The RLOC address configuration details (whether it is manually configured or discovered) on a (P)xTR is displayed in the above table.



**Related Commands**

Command	Description
<b>show ip lisp</b>	Displays the IPv4 LISP configuration status for the local device.

## show lisp instance-id

To display the negative prefix hole in the LISP ALT for an EID within a specified instance-id, use the **show lisp instance-id [0-16777200]** command in privileged EXEC mode.

**show lisp instance-id**

### Command Modes

Privileged EXEC (#)

### Command History

Release	Modification
Cisco IOS XE Dublin 17.11.1a	This command was introduced.

### Usage Guidelines

This command is only used on LISP Map-Server (MS) devices to display the negative prefix hole in the LISP ALT for an EID within a specified instance-id.

### Examples

The following sample output from the show ip lisp instance-id command for the instance-id 123 and EID 2001:db8:c::1.

```
Router# Router# show ipv6 lisp instance-id 123 alt negative-prefix 2001:db8:c::1
Negative mapping system prefix 2001:DB8:C::/46
Router#
```

### Related Commands

Command	Description
<b>eid-prefix (LISP site)</b>	Configures the EID-prefix associated with a LISP site on a Map-Server as part of the LISP Site configuration process.

# show lisp locator-table

To display summary information related to the Locator/ID Separation Protocol (LISP) configuration, use the **show lisp locator-table** command in privileged EXEC mode.

```
show lisp locator-table {default | vrf vrf-name}
```

Syntax Description	default	Displays summary information related to the default table.
	vrf vrf-name	Displays summary information related to the specified virtual routing and forwarding (VRF) table.

**Command Modes** Privileged EXEC (#)

Command History	Release	Modification
	15.1(1)XB6	This command was introduced.
	15.1(4)M	This command was integrated into Cisco IOS Release 15.1(4)M and modified to include the <b>locator-table</b> keyword.
	Cisco IOS XE Release 3.3S	This command was integrated into Cisco IOS XE Release 3.3S and modified to include the <b>locator-table</b> keyword.

## Usage Guidelines

The **locator-table** command creates an association between a LISP instantiation and a VRF table through which the routing locator address space is reachable. When used with the **default** keyword, the **show lisp locator-table** command displays summary information about the default locator table, including any associated locator table or EID instance IDs. When the optional **vrf vrf-name** keyword and argument is included, the **show lisp** command displays summary information related to the specified locator table, including any associated locator table or EID instance IDs.

## Examples

The following is sample output from the **show lisp locator-table default** command:

```
Router# show lisp locator-table default

Router-lisp ID:      0
Locator table:      default
EID instance count: 1
Router#
```

The following is sample output from the **show lisp locator-table vrf** command when using the locator-table VRF option (and a configuration exists for the specified locator table and VRF):

```
Router# show lisp locator-table vrf Cust-1

Router-lisp ID:      1
Locator table:      vrf Cust-1
EID instance count: 1
Router#
```

**Related Commands**

<b>Command</b>	<b>Description</b>
<b>locator-table</b>	Configures the association of a VRF table through which the routing locator address space is reachable to a router LISP instantiation.

# show lisp site



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp server**.

To display configured LISP sites on a Locator/ID Separation Protocol (LISP) map server, use the **show lisp site** command in privileged EXEC mode.

```
show lisp site [{IPv4-dest-EIDIPv4-dest-EID-prefixIPv6-dest-EIDIPv6-dest-EID-prefix}] | [name site-name] | [detail]
```

Syntax Description		
	<i>IPv4-dest-EID</i>	(Optional) Displays LISP site information matching this destination endpoint identifier (EID).
	<i>IPv4-dest-EID-prefix</i>	(Optional) Displays LISP site information matching this destination EID prefix.
	<i>IPv6-dest-EID</i>	(Optional) Displays LISP site information matching this destination EID.
	<i>IPv6-dest-EID-prefix</i>	(Optional) Displays LISP site information matching this destination EID prefix.
	<b>name</b> <i>site-name</i>	(Optional) Displays LISP site information matching this site name.
	<b>detail</b>	(Optional) Increases the detail of all displayed LISP site information when no other parameters are used.

**Command Modes** Privileged EXEC (#)

Command History	Release	Modification
	15.1(1)XB2	This command was introduced.
	Cisco IOS XE Release 2.5.1XB	This command was integrated into Cisco IOS XE Release 2.5.1XB.
	Cisco IOS XE Release 3.3.0S	This command was integrated into Cisco IOS XE Release 3.3.0S.
	15.1(4)M	This command was integrated into Cisco IOS Release 15.1(4)M.

**Usage Guidelines** This command is used on a LISP map server to display information related to configured LISP sites. The displayed output indicates, among other things, whether a site is actively registered.

When the base form of the command is used (**show lisp site**), summary information related to all configured LISP sites is displayed. When the *IPv4-dest-EID* form is used, a longest match is done to return the site with the best matching EID prefix and the displayed information applies specifically to that LISP site. When the *IPv4-dest-EID-prefix* form is used, an exact match is done to return the site configured with the EID prefix and the displayed information applies specifically to that LISP site. When the *site-name* form is used, the displayed information contains all EID prefixes configured for the named LISP site. When the **detail** keyword is added, all available details for the specific command form are presented.

## Examples

The following sample output from the **show lisp site** command displays summary information related to all configured LISP sites:

```
Map-Server# show lisp site

LISP Site Registration Information

Site Name      Last      Up    Who Last      EID Prefix
              Register  Registered
site1-xtr      00:00:04 yes   10.0.2.1     192.168.1.0/24
              00:00:04 yes   10.0.2.1     2001:DB8:A::/48
site2-xtr      00:00:35 yes   10.0.9.1     192.168.11.0/24
              00:00:35 yes   10.0.10.1    2001:DB8:B::/48
```

The following sample output from the **show lisp site dmm-xtr-1** command displays detailed information related specifically to the LISP sites dmm-xtr-1.

```
Map-Server# show lisp site name site1-xtr

Description: LISP Site 1
Allowed configured locators: any
Allowed EID-prefixes:
  EID-prefix: 192.168.1.0/24
    First registered: 00:17:15
    Routing table tag: 0x0
    ETR 10.0.3.1, last registered 00:00:01, no proxy-reply
      Locator  Local  State      Pri/Wgt
      10.0.2.1 no    up         1/50
      10.0.3.1 yes   up         1/50
    ETR 10.0.2.1, last registered 00:00:24, no proxy-reply
      Locator  Local  State      Pri/Wgt
      10.0.2.1 yes   up         1/50
      10.0.3.1 no    up         1/50
  EID-prefix: 2001:DB8:A::/48
    First registered: 00:17:14
    Routing table tag: 0x0
    ETR 10.0.2.1, last registered 00:00:23, no proxy-reply
      Locator  Local  State      Pri/Wgt
      10.0.2.1 yes   up         1/50
      10.0.3.1 no    up         1/50
    ETR 10.0.3.1, last registered 00:00:58, no proxy-reply
      Locator  Local  State      Pri/Wgt
      10.0.2.1 no    up         1/50
      10.0.3.1 yes   up         1/50
```

## Related Commands

Command	Description
<b>show ip lisp</b>	Displays the IPv4 LISP configuration status for the local device.

# show lisp site rloc members



**Note** This command has currently been deprecated and when entered, it will automatically direct you to the updated command and its respective output. This information will be provided through a banner that will appear on screen when you run the previous command. The revised option for this command is **show lisp instance-id [0-16777200] ipv4 server rloc** for IPv4 and **show lisp instance-id [0-16777200] ipv6 server rloc** for IPv6.

To display Routing Locator (RLOC) address configuration details (such as RLOC endpoint identifier [EID] instance membership registration) for a Locator/ID Separation Protocol (LISP) site, use the **show lisp site rloc members** command in privileged EXEC mode.

**show lisp site rloc members** [**registrations** [*rloc-address*] | **instance-id** *iid*]

## Syntax Description

<b>registrations</b>	(Optional) Specifies that RLOC EID instance membership registration details be displayed.
<i>rloc-address</i>	(Optional) IPv4 or IPv6 RLOC address. If you want to view details for a specific RLOC address, you need to use this option.
<b>instance-id</b> <i>iid</i>	(Optional) Specifies the instance ID for which the RLOC addresses will be displayed.

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
15.5(1)T	This command was introduced.
Cisco IOS XE Release 3.14S	This command was integrated into Cisco IOS XE Release 3.14S.

## Usage Guidelines

### Examples

The following sample output from the **show lisp site rloc members** command displays RLOC address configuration details for the instance ID 0:

```
Device# show lisp site rloc members

LISP RLOC membership for EID table default (IID 0), 2 entries

RLOC                               Origin                               Valid
10.0.1.2                             registration                           Yes
10.0.2.2                             config & registration                   Yes
```

The **Origin** column displays configuration details of the RLOC member. If an RLOC address is manually configured, automatically gleaned from received registrations, or both, the details are displayed. The **Valid** column shows whether the RLOC is a valid member that is distributed to (P)xTRs. A listed RLOC may not be valid if it is gleaned from registrations but the “override” option is used in the “modify-discovered” configuration and the specified locator-set does not include the RLOC.

---

**Related Commands**

Command	Description
<b>show ip lisp</b>	Displays the IPv4 LISP configuration status for the local device.



# show lisp session

To display a current list of reliable transport (TCP) sessions, use the **show lisp session** command in privileged EXEC mode.

```
show lisp [session [established] | vrf [vrf-name [session [peer-address] ] ] ]
```

Syntax Description	session	(Optional) Specifies that reliable transport session information is displayed. If there are multiple transport sessions due to multiple roles, you can view information for all the sessions.
	established	(Optional) Displays transport session information for established connections.
	vrf vrf-name	(Optional) Specifies the VRF instance. The transport session information for this VRF instance will be displayed.
	peer-address	(Optional) IPv4 or IPv6 peer address. A transport session is established between a LISP (P)xTR and each Map-Server it peers with, and is used to communicate RLOC membership information in support of the LISP data plane security feature.

**Command Modes** Privileged EXEC (#)

Command History	Release	Modification
	15.5(1)T	This command was introduced.
	Cisco IOS XE Release 3.14S	This command was integrated into Cisco IOS XE Release 3.14S.

## Usage Guidelines

### Examples

The following sample output from the **show lisp session** command displays transport session information for a LISP VRF instance:

```
Device# show lisp session

Sessions for VRF default, total: 8, established: 7
Peer                State    Up/Down    In/Out    Users
2001:DB8:A:1::2    Up       00:04:13   2/7       2
2001:DB8:A:2::2    Up       00:04:13   2/7       2
2001:DB8:A:3::2    Up       00:03:53   2/7       2
2001:DB8:B:1::2    Up       00:04:04   2/6       2
2001:DB8:B:2::2    Init     never      0/0       1
2001:DB8:C:1::2    Up       00:03:55   2/6       2
2001:DB8:C:2::2    Up       00:03:54   2/6       2
2001:DB8:E:F::2    Up       00:04:04   6/19     4
```

---

**Related Commands**

Command	Description
<b>show ip lisp</b>	Displays the IPv4 LISP configuration status for the local device.