



IPv6 ACL Undetermined-Transport Support

The IPv6 ACL Undetermined-Transport Support feature helps in dropping misconfigured packets where the complete upper layer header is not present.

- [Restrictions for IPv6 ACL Undetermined-Transport Support, on page 1](#)
- [Information about IPv6 ACL Undetermined-Transport Support, on page 1](#)
- [How to Configure IPv6 ACL Undetermined-Transport Support, on page 2](#)
- [Configuration Examples for IPv6 ACL Undetermined-Transport Support, on page 3](#)
- [Additional References for IPv6 ACL Undetermined-Transport Support, on page 3](#)
- [Feature Information for ACL Template, on page 4](#)

Restrictions for IPv6 ACL Undetermined-Transport Support

- The undetermined-transport option is supported only for Cisco Application Control Engines (ACE) with deny action and IPv6 protocol.
- Undetermined transport is not applied on nonfirst fragment packets.

Information about IPv6 ACL Undetermined-Transport Support

IPv6 ACL Undetermined-Transport

Unintended misconfigurations by users or malicious attacks on the network may cause operational problems for hosts on the network.

Upper layer header is placed at the end of Extended Header (EH) chain in IPv6 packet, as it described in RFC 2460. If the complete upper layer header is not present in the IPv6 packet, then the router cannot process the packet. These packets may be misconfigured, corrupted, or malicious packets.

You may choose to drop these packets using IPv6 ACL with undetermined-transport option.

How to Configure IPv6 ACL Undetermined-Transport Support

Configuring IPv6 ACL Undetermined-Transport Support

SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **ipv6 access-list *acl-name***
4. **deny ipv6 {*src-addr* | any} {*dest-addr* | any} [undetermined-transport]**
5. **end**

DETAILED STEPS

	Command or Action	Purpose
Step 1	enable Example: Device> enable	Enables privileged EXEC mode. <ul style="list-style-type: none"> • Enter your password if prompted.
Step 2	configure terminal Example: Device# configure terminal	Enters global configuration mode.
Step 3	ipv6 access-list <i>acl-name</i> Example: Device(config)# ipv6 access-list acl1	Configures IPv6 access list.
Step 4	deny ipv6 {<i>src-addr</i> any} {<i>dest-addr</i> any} [undetermined-transport] Example: Device(config-ipv6-acl)# deny ipv6 2001:DB8:0300:0201::/32 2001:DB8:1:1::/64 undetermined-transport	Sets deny condition for an IPv6 access list as undermined transport.
Step 5	end Example: Device(config-ipv6-acl)# end	Returns to privileged EXEC mode.

Configuration Examples for IPv6 ACL Undetermined-Transport Support

Example: Example for IPv6 ACL Undetermined-Transport Support

```
Device> enable
Device# configure terminal
Device(config)# ipv6 access-list acl1
Device(config-ipv6-acl)# deny ipv6 2001:DB8:0300:0201::/32 2001:DB8:1:1::/64
undetermined-transport
Device(config-ipv6-acl)# end
```

Additional References for IPv6 ACL Undetermined-Transport Support

Related Documents

Related Topic	Document Title
Cisco IOS commands	Cisco IOS Master Command List, All Releases
IP access list commands	<i>Cisco IOS Security Command Reference</i>
Configuring IP access lists	“Creating an IP Access List and Applying It to an Interface”

Standards and RFCs

Standards/RFCs	Title
RFC 2460	Internet Protocol, Version 6 (IPv6) Specification

Technical Assistance

Description	Link
The Cisco Support and Documentation website provides online resources to download documentation, software, and tools. Use these resources to install and configure the software and to troubleshoot and resolve technical issues with Cisco products and technologies. Access to most tools on the Cisco Support and Documentation website requires a Cisco.com user ID and password.	http://www.cisco.com/cisco/web/support/index.html

Feature Information for ACL Template

The following table provides release information about the feature or features described in this module. This table lists only the software release that introduced support for a given feature in a given software release train. Unless noted otherwise, subsequent releases of that software release train also support that feature.

Use Cisco Feature Navigator to find information about platform support and Cisco software image support. To access Cisco Feature Navigator, go to www.cisco.com/go/cfn. An account on Cisco.com is not required.

Table 1: Feature Information for ACL Template

Feature Name	Releases	Feature Information
IPv6 ACL Undetermined-Transport Support	Cisco IOS XE Release 3.15	The IPv6 ACL Undetermined-Transport Support feature helps in dropping misconfigured packets, where the complete upper layer header is not present. No commands were introduced or modified.