How to Configure Meeting Title Displayed in the Lobby for CMS

Contents

Introduction

Prerequisites

Requirements

Components Used

Configuration

Verify

Troubleshoot

Introduction

This document describes the steps required to configure the meeting name to be displayed in the lobby of the conference for Cisco Meeting Server (CMS).

Prerequisites

Requirements

Cisco recommends that you have knowledge of these topics:

- CMS general configuration
- CMS Application Programing Interface (API)

Components Used

The information in this document is based on CMS version 3.2.

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live, ensure that you understand the potential impact of any command.

Configuration

Step 1. Create a new CallLegProfile via API.

- 1. Access CMS via Webadmin and naavigate to Configuration/api/v1/callLegProfiles.
- 2. Create new CallLegProfile and modify next parameters as shown in the image:

name: TECHZONE

meetingTitlePosition: middle

Note: The **meetingTitlePosition** has the next options available to be configured: **top**, **bottom** and **middle**.

« return to object list

/api/v1/callLegProfiles/127874d9-ee5a-4679-8173-97b80bd06754

Related objects: /api/v1/callLegProfiles

/api/v1/callLegProfiles/127874d9-ee5a-4679-8173-97b80bd06754/usage

Table view	XML view
------------	----------

Obj	ect configuration		
	name	TECHZONE	
	meetingTitlePosition	middle	
${\it allow All Presentation Contribution Allowed}$	☐ <unset> ∨</unset>		
change Join Audio Mute Override Allowed	☐ <unset> ∨</unset>		
recordingControlAllowed	☐ <unset> ∨</unset>		
streamingControlAllowed	☐ <unset> ∨</unset>		
name	TECHZONE		- present
maxCallDurationTime			
qualityMain	☐ <unset> ∨</unset>	/	
qualityPresentation	☐ <unset> <</unset>	/	
participantCounter	☐ <unset> ∨</unset>		
layoutTemplate			Choose
controlRemoteCameraAllowed	☐ <unset> ∨</unset>		
audioGainMode	☐ <unset> ∨</unset>		
meetingTitlePosition	☐ middle ∨ - ı	present	
chat Contribution Allowed	☐ <unset> ∨</unset>		
	Modify		

Step 2. Assign the CallLegProfile to the space.

- 1. Open the Webadmin and navigate to Configuration/api/v1/coSpaces.
- 2. Select the space required to assign the CallLegProfile created in Step 1.

CallLegProfile: 127874d9-ee5a-4679-8173-97b80bd06754

« return to object list

/api/v1/coSpaces/7acfa0e8-1613-47bc-a274-4e2c7024dbbf


Related objects: /api/v1/coSpaces

/api/v1/coSpaces/7acfa0e8-1613-47bc-a274-4e2c7024dbbf/accessMethods
/api/v1/coSpaces/7acfa0e8-1613-47bc-a274-4e2c7024dbbf/coSpaceUsers
/api/v1/coSpaces/7acfa0e8-1613-47bc-a274-4e2c7024dbbf/diagnostics
/api/v1/coSpaces/7acfa0e8-1613-47bc-a274-4e2c7024dbbf/meetingEntryDetail
/api/v1/coSpaces/7acfa0e8-1613-47bc-a274-4e2c7024dbbf/metadata






/api/v1/coSpaces/7acfa0e8-1613-47bc-a274-4e2c7024dbbf




Verify

Step 1. Verify if the configuration is applied successfully..

1. Start a call to the space where the **CallLegProfile** is assigned and you must see the meeting title displayed in the lobby as shown in the image:



The parameter **meetingTitleDisplayed** configured with **Top** option is shown in the next image:.



Troubleshoot

There is currently no specific troubleshooting information available for this configuration.				