Configure Display Name in Communications Manager (CUCM) Self-Care Portal

Contents

Introduction

Prerequisites

Requirements

Components Used

Configure

Verify

Troubleshoot

Introduction

This documented describes the new Display Name feature introduced in Communications Manager (CUCM) 11.5. You can now assign a personal Display Name in the self-care portal instead of the CUCM End User configuration page.

Prerequisites

Requirements

Cisco recommends that you have knowledge of these topics:

- Cisco CallManager End User configuration
- Cisco Self-Care Portal

Components Used

The information in this document is based on Cisco CallManager 11.5 and later.

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live ensure that you understand the potential impact of any command.

Configure

Configure Display Name in Self-Care Portal

Step 1. Log in to the Self- Care portal page with the required credentials.

Step 2. Navigate to **General Settings > Display Name.**

Display Name Image

isplay Name	
nter the Display Name you	want others to see.
Display Name:	Animesh Lochan
Save Cancel	


Step 3. Enter the required value in the space and select Save.

Note: For a LDAP integrated User the Display Name field is greyed out and cannot be edited.

Step 4. As soon as you select **Save** the End User configuration page on the CUCM End User Configuration Administration page updates.

Architecture between Self-Care Portal and CUCM

The communication between CUCM and the Self-Care Portal takes place through a RESTful Application Programming Interface (API) based set of operations known as User Data Services (UDS). It is represented in this image:



UDS runs the database queries on CUCM to save the Display Name Data as entered on the Self-Care Portal.


Verify

Query the XML file from the browser for a specific User object. View the XML file the UDS uses for data exchange with the URL, https://{host}:8443/cucm-uds/users?displayname="enter_text_here"

This XML file does not appear to have any style information associated with it. The document tree is shown below.

```
▼<users uri="https://10.106.110.2:8443/cucm-uds/users" version="11.5.0" start="0" requestedCount="64" returnedCount="1" totalCount="1">
    ▼<user uri="https://10.106.110.2:8443/cucm-uds/user/user1">
    <id>0ba61991-9631-347d-58c2-ef63c3661fd0</id>
       <userName>user1</userName>
       <firstName/>
       <lastName>user1
      <middleName/>
      <nickName/>
      <displayName>Animesh Lochan</displayName>
      <phoneNumber/>
<homeNumber/>
      <mobileNumber/>
       <email/>
      <directoryUri/>
<msUri/>
      <department/>
      <manager/>
<title/>
      <pager/>
    </user>
  </users>
```

Image: The Display Name field (boxed in red) automatically updates with the same value entered on the Self-Care portal page



Troubleshoot

- Step 1. Verify the changes to Display Name on the Self-Care Portal are Saved.
- Step 2. Verify there are no database replication problems with the command **utils dbreplication runtimestate** in the command line interface (CLI) of the CUCM publisher.
- Step 3. Before you can access the Cisco Unified Communications Self Care Portal, you must use Cisco Unified Communications Manager Administration to add the user to a standard Cisco Unified Communications Manager End User group.