



# Deactivate Secure Email Threat Defense

## Message Source: Microsoft 365

To deactivate Secure Email Threat Defense when you have Microsoft as your message source, there are two main tasks:

- Delete your Secure Email Threat Defense journal entry from Microsoft 365 Admin Center
- Delete the Secure Email Threat Defense application from your Microsoft Azure tenant

## Delete Your Secure Email Threat Defense Journal Rule

To delete your Secure Email Threat Defense journal rule:

1. Go to your Microsoft 365 Admin Center <https://admin.microsoft.com/AdminPortal/Home#/homepage>.
2. Navigate to **Admin centers** > **Compliance** > **Data lifecycle management** > **Exchange (legacy)** > **Journal rules**.
3. Select the Secure Email Threat Defense journal rule, then click **Delete**. Select **Yes** to confirm you want to delete the journal rule.

## Delete the Secure Email Threat Defense Application from Azure

To delete the Secure Email Threat Defense application from Azure:

1. Go to [portal.azure.com](https://portal.azure.com).
2. Search for and select **Enterprise applications**.  
**Note:** If you are using an older view in Azure, this may be called **App registrations**.
3. Locate and select the **Cisco Secure Email Threat Defense** and/or **Cisco Secure Email Threat Defense (Read Only)** application.
4. In the left pane, select **Properties**.
5. Click the **Delete** button, then select **Yes** to confirm you want to delete the Secure Email Threat Defense app.

## Message Source: Gateway

To deactivate Secure Email Threat Defense when you are using a Gateway as your message source, there are two main tasks:

- Configure your Gateway to stop sending messages to Secure Email Threat Defense
- Delete the Secure Email Threat Defense application from your Microsoft Azure tenant (not necessary for No Authentication mode)

Message Source: Gateway

## Configure your Gateway to Stop Sending Messages

To configure your Gateway to stop sending messages to Secure Email Threat Defense:

1. In your Secure Email Cloud Gateway console, go to **Security Services > Threat Defense Connector**.
2. Set **Threat Defense Connector** to **Disabled**.

## Delete the Secure Email Threat Defense Application from Azure

To delete the Secure Email Threat Defense application from Azure:

1. Go to [portal.azure.com](https://portal.azure.com).
2. Search for and select **Enterprise applications**.  
**Note:** If you are using an older view in Azure, this may be called **App registrations**.
3. Locate and select the **Cisco Secure Email Threat Defense** and/or **Cisco Secure Email Threat Defense (Read Only)** application.
4. In the left pane, select **Properties**.
5. Click the **Delete** button, then select **Yes** to confirm you want to delete the Secure Email Threat Defense app.