

Verificar la versión de las actualizaciones en la interfaz de línea de comandos (CLI) de Firepower

Contenido

[Introducción](#)

[Prerequisites](#)

[Abreviaturas](#)

[Verificar versión de actualizaciones diferente](#)

[1. Versión del software del producto](#)

[2. Versión de actualización de SRU y VDB](#)

[3. Versión de actualización de GeoDB](#)

Introducción

Este documento describe cómo verificar diferentes versiones de actualizaciones en Firepower Command Line Interface (CLI).

Prerequisites

Cisco recomienda que conozca estos productos:

- Centro de administración Firepower (FMC)
- Firepower Threat Defense (FTD)

Abreviaturas

- Centro de administración Firepower (FMC)
- Firepower Threat Defense (FTD)
- Actualización de reglas seguras o actualización de reglas de Sourcefire (SRU)
- Paquete de seguridad ligero (LSP)
- Base de datos de vulnerabilidad (VDB)
- Base de datos de ubicación geográfica (GeoDB)

Verificar versión de actualizaciones diferente

1. Versión del software del producto

En FMC y FTD CLI, puede verificar la versión del software del producto que se está ejecutando mediante el comando:

```
show version
```

Ejemplo: Salida de comando de la CLI de FMC.

```
Copyright 2004-2023, Cisco and/or its affiliates. All rights reserved.  
Cisco is a registered trademark of Cisco Systems, Inc.  
All other trademarks are property of their respective owners.
```

```
Cisco Firepower Extensible Operating System (FX-OS) v2.12.0 (build 499)  
Cisco Secure Firewall Management Center for VMware v7.2.4 (build 169)
```

```
>  
> show version  
-----[ FMC ]-----  
Model : Secure Firewall Management Center for VMware (66) Version 7.2.4 (Build 169) <-  
UUID : 6308d00c-54c3-11ee-a889-c4b0f35cec33  
Rules update version: 2023-10-02-002-vrt  
LSP version : lsp-rel-20231002-1553  
VDB version : 372  
-----
```

Ejemplo: Salida de comando de FTD CLI.

```
Copyright 2004-2022, Cisco and/or its affiliates. All rights reserved.  
Cisco is a registered trademark of Cisco Systems, Inc.  
All other trademarks are property of their respective owners.
```

```
Cisco Firepower Extensible Operating System (FX-OS) v2.10.1 (build 1400)  
Cisco Firepower Threat Defense for VMware v7.0.5 (build 72)
```

```
>  
> show version  
-----[ FTD ]-----  
Model : Cisco Firepower Threat Defense for VMware (75) Version 7.0.5 (Build 72) <- - Di  
UUID : 48797b40-463e-11ed-92b0-d0e26b47dcc4  
Rules update version : 2023-10-02-002-vrt  
VDB version : 372  
-----
```

2. Versión de actualización de SRU y VDB

En FMC y FTD CLI, puede verificar la versión de actualización de SRU (Snort2) y LSP (Snort3) que se está ejecutando actualmente, y la versión de VDB mediante el comando:

show version

Ejemplo: Salida de comando de la CLI de FMC.

Copyright 2004-2023, Cisco and/or its affiliates. All rights reserved.
Cisco is a registered trademark of Cisco Systems, Inc.
All other trademarks are property of their respective owners.

Cisco Firepower Extensible Operating System (FX-OS) v2.12.0 (build 499)
Cisco Secure Firewall Management Center for VMware v7.2.4 (build 169)

```
>
> show version
-----[ FMC ]-----
Model           : Secure Firewall Management Center for VMware (66) Version 7.2.4 (Build 169)
UUID            : 6308d00c-54c3-11ee-a889-c4b0f35cec33
Rules update version: 2023-10-02-002-vrt          <- - Display installed SRU (Snort2) vers
LSP version     : lsp-rel-20231002-1553          <- - Display installed LSP (Snort3) ver
VDB version     : 372                            <- - Display running VDB version.
-----
```

Ejemplo: Salida de comando de FTD CLI Snort2.

Copyright 2004-2022, Cisco and/or its affiliates. All rights reserved.
Cisco is a registered trademark of Cisco Systems, Inc.
All other trademarks are property of their respective owners.

Cisco Firepower Extensible Operating System (FX-OS) v2.10.1 (build 1400)
Cisco Firepower Threat Defense for VMware v7.0.5 (build 72)

```
>
> show version
-----[ FTD ]-----
Model           : Cisco Firepower Threat Defense for VMware (75) Version 7.0.5 (Build 72)
UUID            : 48797b40-463e-11ed-92b0-d0e26b47dcc4
Rules update version : 2023-10-02-002-vrt          <- - Display running SRU (Snort2) vers
VDB version     : 372                            <- - Display running VDB version.
-----
```

Ejemplo: Salida de comando de FTD CLI Snort3.

Copyright 2004-2022, Cisco and/or its affiliates. All rights reserved.
Cisco is a registered trademark of Cisco Systems, Inc.
All other trademarks are property of their respective owners.

Cisco Firepower Extensible Operating System (FX-OS) v2.12.0 (build 8)
Cisco Firepower Threat Defense for VMware v7.2.0 (build 18)

```
>
> show version
```

```

-----[ FTD ]-----
Model       : Cisco Firepower Threat Defense for VMware (75) Version 7.2.0 (Build 18)
UUID        : c04f9496-db0e-11ed-81a1-942878af0a8c
LSP version : lsp-rel-20231002-1553                <- - Display running LSP (Snort3) vers
VDB version : 372                                  <- - Display running VDB version.
-----

```

3. Versión de actualización de GeoDB

En FMC y FTD CLI (en modo experto), puede verificar la versión actual de GeoDB mediante el comando:

```
cat /var/sf/geodb/country_code_map_version
```

Ejemplo: Salida de comando de la CLI de FMC.

Copyright 2004-2023, Cisco and/or its affiliates. All rights reserved.
Cisco is a registered trademark of Cisco Systems, Inc.
All other trademarks are property of their respective owners.

```

Cisco Firepower Extensible Operating System (FX-OS) v2.12.0 (build 499)
Cisco Secure Firewall Management Center for VMware v7.2.4 (build 169)
>
> expert
rirana@FMC:~$ sudo su -
Password:
root@FMC:~#
root@FMC:~# cd /var/sf/geodb/
root@FMC:/var/sf/geodb#
root@FMC:/var/sf/geodb# cat country_code_map_version                <- - To display running GeoDB update version
2023-09-25-100                                                    <- - FMC GeoDB update version is 2023-09-25-

```

Ejemplo: Salida de comando de FTD CLI.

Copyright 2004-2022, Cisco and/or its affiliates. All rights reserved.
Cisco is a registered trademark of Cisco Systems, Inc.
All other trademarks are property of their respective owners.

```

Cisco Firepower Extensible Operating System (FX-OS) v2.10.1 (build 1400)
Cisco Firepower Threat Defense for VMware v7.0.5 (build 72)
>
> expert
FTD:~$ sudo su -
Password:
root@FTD:~#
root@FTD:~# cd /var/sf/geodb/
root@FTD:geodb#
root@FTD:geodb# cat country_code_map_version                <- - To display running GeoDB update version.
2023-09-25-100                                                    <- - FTD GeoDB update version is 2023-09-25-1

```


Acerca de esta traducción

Cisco ha traducido este documento combinando la traducción automática y los recursos humanos a fin de ofrecer a nuestros usuarios en todo el mundo contenido en su propio idioma.

Tenga en cuenta que incluso la mejor traducción automática podría no ser tan precisa como la proporcionada por un traductor profesional.

Cisco Systems, Inc. no asume ninguna responsabilidad por la precisión de estas traducciones y recomienda remitirse siempre al documento original escrito en inglés (insertar vínculo URL).