

Configure Idle User Logout Timer in EPNM GUI

Contents

[Introduction](#)

[Prerequisites](#)

[Requirements](#)

[Components Used](#)

[Configure](#)

[System Level](#)

[User Level](#)

Introduction

This document describes the steps to change the idle user logout timer in Evolved Programmable Network Manager (EPNM).

Prerequisites

Requirements

Cisco recommends that you have knowledge of EPN Manager.

Note: Need to have access to EPNM GUI.

Components Used

The information in this document is based on EPNM.

The information in this document was created from the devices in a specific lab environment. All of the devices used in this document started with a cleared (default) configuration. If your network is live, ensure that you understand the potential impact of any command.

Configure

You must make this change at two levels (System Level and User Level).

System Level

Navigate to **Administration > Setting > System Settings**. Under **General**, select **Server** and change the timeout value as shown in this image:



System Settings

← Search All

- Help Us Improve
- Job Approval
- Proxy
- Login Disclaimer
- Report
- Server**
- Software Update
- Support Request
- Cisco DNA Center coexistence
- User Defined Fields
- Mail and Notification
 - Change Audit Notification
 - Mail Server Configuration

General
Server

The page will automatically reload once the Global Idle Timeout settings are changed and saved.

Global Idle Timeout

Logout all idle users

Logout all idle users after

- 15 min
- 10 min
- 15 min
- 30 min
- 60 min**
- 120 min
- 600 min

Restart application

Restart EPN M

FTP

Enable Disable

Listening on Port 21

User Level

Click the Settings icon on the top right and select **My Preferences**.

16 root - ROOT-DOMAIN

Logged In As root

- Log out
- Change Password
- Set Current Page As Home
- My Preferences**
- Support Cases

Virtual Domain: **ROOT-DOMAIN**

Change the timeout value as desired and click **Save**.

General

Alarms & Events

Chassis racks to display ?

▼ Service Provisioning

Default Technology ?

Default Service Type ?

▼ Device Inventory List View

Device List Table Refresh Interval

▼ Mobility Services Engine

Use MSE Admin View ?

▼ User Idle Timeout

Logout idle user ?

Logout idle user after ?

Save

Cancel

Reset Default System Settings

Log out and log back in for the changes to take effect.