



# Cisco Unity Connection SRSV Administration - Networking Settings Interface

See the following sections:

- [Central Server Configuration, page 12-1](#)
- [Configuring Central Server in Unity Connection SRSV, page 12-2](#)

## Central Server Configuration

Revised August, 2014

**Table 12-1** Central Server Configuration Page

Field	Description
Server Address	<p>The Fully Qualified Domain Name (FQDN) address of the Cisco Unity Connection server, server host name or FQDN.</p> <p>To implement the Unity Connection SRSV High Availability functionality, you must mention a common DNS A Record for both publisher and subscriber for central Unity Connection server.</p> <p>This Common DNS A record for unity connection Cluster should also be a part of Central Unity connection Certificate as “Subject Alternate Name” or you can also enable <b>Ignore Certificate Error</b> feature in Unity Connection SRSV.</p> <p>For more information on “Subject Alternate Name” see <i>Security Guide for Cisco Unity Connection, Release 10.x</i> at <a href="http://www.cisco.com/c/en/us/td/docs/voice_ip_comm/connection/10x/security/guide/10xcucsecx/10xcucsec065.html">http://www.cisco.com/c/en/us/td/docs/voice_ip_comm/connection/10x/security/guide/10xcucsecx/10xcucsec065.html</a>.</p> <p>For more information on ignoring certificate error, see <a href="http://www.cisco.com/c/en/us/td/docs/voice_ip_comm/connection/10x/srsv/guide/10xcucsrsvx/10xcucsrsv120.html#wp1076665">http://www.cisco.com/c/en/us/td/docs/voice_ip_comm/connection/10x/srsv/guide/10xcucsrsvx/10xcucsrsv120.html#wp1076665</a>.</p> <p>For information on managing SAN Certificates, see <a href="http://www.cisco.com/c/en/us/td/docs/voice_ip_comm/connection/10x/os_administration/guide/10xcucosagx/10xcucosag060.html#pgfId-1053402">http://www.cisco.com/c/en/us/td/docs/voice_ip_comm/connection/10x/os_administration/guide/10xcucosagx/10xcucosag060.html#pgfId-1053402</a>.</p>
Test	<p>Confirms the connectivity with the central Unity Connection server. On the successful result, the status “Central Server Active” is displayed.</p>

# Configuring Central Server in Unity Connection SRSV

## To Configure Central Unity Connection Server in Unity Connection SRSV

- 
- Step 1** In Cisco Unity Connection SRSV Administration, expand **Networking** and select **Central Server Configuration**.
- Step 2** On the Central Server Configuration page, enter the applicable settings and select **Save**.



---

**Note** A branch can be connected to only one central Unity Connection.

---