



VES Adapter Config Mode Command Reference

- [ves-adapter](#), on page 1
- [ves-adapter measurement-group](#), on page 2
- [ves-adapter measurement-group measurement](#), on page 2

ves-adapter

Configures VES Adapter parameters.

Command Modes Exec > Global Configuration

Syntax Description

```
ves-adapter enable { false | true } [ [ [ url ves_listener_url | user-name  
ves_listener_user_name | password ves_listener_password ] | measurement-interval  
measurement_interval ] | [ measurement-group [ name group_name | measurement [  
name measurement_name ] query measurement_query ] ] | measurement-group  
measurement_group_name [ measurement measurement_name | query measurement_query ] ]
```

enable { false | true}

Specify to enable or disable the VES Adapter.

Must be one of the following:

- **false**
- **true**

Default Value: false.

measurement-interval *measurement_interval*

Specify the interval to fetch measurements in seconds.

Must be an integer in the range of 1-86400.

Default Value: 300.

password *ves_listener_password*

Specify the VES Listener password.

ves-adapter measurement-group

Must be a string.

url ves_listener_url

Specify the VES Listener URL with path.

Must be a string.

user-name ves_listener_user_name

Specify the VES Listener user name.

Must be a string.

Usage Guidelines Use this command to configure VES Adapter parameters.

ves-adapter measurement-group

Configures the list of additional measurement groups.

Command Modes Exec > Global Configuration

Syntax Description **ves-adapter enable { true } measurement-group *group_name***

group_name

Specify the additional measurement group name.

Must be a string.

Usage Guidelines Use this command to configure the list of additional measurement groups.

ves-adapter measurement-group measurement

Configures the list of additional measurement queries.

Command Modes Exec > Global Configuration

Syntax Description **ves-adapter enable { true } measurement-group *group_name* { measurement_name *query measurement_query*}**

query measurement_query

Specify the query to execute in Promo QL format.

Must be a string.

measurement_name

Specify the measurement name.

Must be a string.

Usage Guidelines Use this command to configure the list of additional measurement queries.

ves-adapter measurement-group measurement