Hoe stelt u de functies voor nu conferentie in CUCM 11.X in

Inhoud

Inleiding Voorwaarden Vereisten Gebruikte componenten Achtergrondinformatie Configureren Configuraties Verifiëren Problemen oplossen

Inleiding

Dit document beschrijft een nieuwe **conferentie** van de eigenschappen **nu**, in Cisco Unified Communications Manager (CUCM).

Voorwaarden

Vereisten

Cisco raadt u aan om kennis te hebben van Media resources op Call Manager.

Gebruikte componenten

De informatie in dit document is gebaseerd op CUCM versie 11.5.0.99838-4.

De informatie in dit document is gebaseerd op de apparaten in een specifieke laboratoriumomgeving. Alle apparaten die in dit document worden beschreven, hadden een opgeschoonde (standaard)configuratie. Als uw netwerk live is, moet u de potentiële impact van elke opdracht begrijpen.

Achtergrondinformatie

De eigenschap van de Conferentie nu staat zowel externe als interne bezoekers toe om zich bij een conferentie aan te sluiten door een Van de Conferentie Nu IVR Aantal van de Map te draaien, dat een gecentraliseerd aantal van de conferentiehulp is. Een IVR-toepassing leidt de beller om zich bij de conferentie aan te sluiten door aankondigingen af te spelen. Nadat de host zowel het vergadernummer als de PIN correct heeft ingevoerd, wordt een conference bridge toegewezen op basis van de Media Resource Group List (MRGL) van de host. Deelnemers die meedoen voor de vergadering begint, worden omgeleid naar dezelfde conferentiebrug. De gastheer kan de code van de Toegang van de Aanhangers voor een veilige conferentie instellen.

Configureren

Dit is een procedure om de functie **Conference Now** te configureren.

Configuraties

Stap 1. Configureer de conferentie nu.

Navigeer om routing > Conference Now te bellen, zoals in de afbeelding wordt getoond:

ahaha	Cisco Unified CM Adm	ninistration
cisco	For Cisco Unified Communications	Solutions
System 👻	AAR Group Dial Rules	anced Features ▼ Device ▼ Application ▼ User Management ▼ Bulk Administration ▼ Help ▼
⚠	Route Filter	ice is configured. This is required to recover your system in case of
Cisc System	SIP Route Pattern Class of Control Intercom	istration
VMware	Client Matter Codes Forced Authorization Codes Emergency Location	n(R) CPU E5-4669 v3 @ 2.10GHz, disk 1: 120Gbytes, 5120Mbytes RAM, Partitions aligne
User c last l	Translation Pattern	ust 27, 2016 11:52:28 AM IST, to node 10,106 99,199, from 10,106,120,156 using HTTPS
Copyright © All rights res	Call Park Directed Call Park Call Pickup Group	131 27, 2010 11.32.20 AM 131, to hode 10.100.33.133, hom 10.130.120.130 daing m 173
This product exporters, d	Directory Number Meet-Me Number/Pattern	ubject to United States and local country laws governing import, export, transfer and use. Delivery of ompliance with U.S. and local country laws. By using this product you agree to comply with applicable
A summary (Conference Now	c products may be found at our <u>Export Compliance Product Report</u> web site.
For Cisco Te	Dial Plan Installer Route Plan Report Transformation Mobility	I Support web site.
	Logical Partition Policy Configuration	

Hier houdt de **Conference Now** DN in partitie die toegankelijk is met respectievelijke Call Search Space (CSS).

System Call Routing Media Resources Advanced Features	s ▼ Device ▼ Application ▼ User Management ▼ B	ulk Administration Help
Conference Now Configuration		
Save 🗶 Delete		
Status: Ready		
Conference Now Configuration		
Conference Now IVR Directory Number*	3030	
Route Partition	PT-CUG	
Description]
Maximum Wait Time For Host Until Participant is Disconnected st	15	Minutes
MOH Source While Participant is Waiting	1-SampleAudioSource	-
Save Delete		
(i) *- indicates required item.		

Stap 2. Nu gebruik onder Apparaat en kies de gebruikershandleiding.

Navigeren in naar **apparaat >Telefonisch** en naar het apparaat zoeken.

cisco	Cisco U For Cisco Un	nified CM Ad	dministration	1			
System 💌	Call Routing 👻	Media Resources 👻	Advanced Features 💌	Device	Application	User Managem	ment Bulk Administration Help
Find and L	ist Phones			СТ	Route Point		
Add Ne	ew			Ga	ekeeper		
				Ga	eway		
Phone				Ph	one		
Find Phone	where Device	Name	begins with	Tru	nk		ar Filter
	intere beriet		begins men	Re	note Destination		
				De	ice Settings	•	active query. Please enter your search criteria using the options above.
Add New	,						

Selecteer het juiste apparaat.

System •	Call Routing 👻 Media Reso	urces • Advanced Features • Device •	Application 👻 User Management 👻	Bulk Administration 👻 I	Help 👻				
Find and	nd and List Phones Related Links: Actively Logged In Device Report 💌 🙃								
Add N	Add New 🏢 Select All 🔛 Clear All 🙀 Delete Selected 🍲 Reset Selected 🥒 Apply Config to Selected								
Status -									
(i) 7 rec	cords found								
Phone	(1 - 7 of 7)							Roy	vs per Page 50 🔻
Find Phone	e where Device Name	▼ begins with ▼	Find Clear Filter	• •					
		Select	item or enter search text 🔻						
		Device Name(Line) *	Description	Device Pool	Device Protocol	Status	IPv4 Address	Сору	Super Copy
		ANAAAAAAAAAAAOOO	ANAAAAAAAAAA000	Default	SCCP	None	None		
		CSESAKALEKA		Default	SIP	None	None	6	1
	() ()	SEP001121FF6F2E	SEP001121FF6F2E	Default	SCCP	Registered with CUCM-PUB	10.106.99.231	ß	1
	7841	SEP00E16DBASED5	Auto 3003	HQ	SIP	Registered with CUCM-PUB	10.106.99.230	ß	1
	() ()	SEP44E4D9458511	Auto 3004	Default	SIP	None	None	ß	1
	CIPC	SEP54EE7581271D		Default	SCCP	None	None	D.	1
	() 1200	SEPA40CC3957CC7	Auto 3002	Default	SIP	Registered with CUCM-PUB	10.106.99.236	ß	1
Add Nev	w Select All Clear Al	Delete Selected Reset Selected	Apply Config to Selected						

Phone	Configuration			Related Links: Back To Find/List	▼ Go
🔒 Si	we 🗙 Delete 📋 Copy 蠀 Reset 🧷 Apply Cor	nfig 🕞 Add New			
Status () s					
• Assoc	Modify Button Items	Phone Type Product Type: Cisco 9951 Device Protocol: SIP			
2 3	Comp Line [2] - 3006 in PT-CUG	Real-time Device Status Registration: Registered with Cisco IPv4 Address: 10.106.99.236	Unified Communications Manager CUCM-PUB		
4 5	ශික <u>g.cisco1@cisco.com</u> ශික <u>g.Add a new SD</u>	Active Load ID: sip9951.9-4-25R2-2 Inactive Load ID: sip9951.9-4-2-13 Download Status: Unknown			
6	Add On Module(s) None None	Device Information			
8 9	None	Device is trusted MAC Address *	A40CC3957CC7		
10	None	Description	Auto 3002		

Selecteer hier **Eigenaar** als **Gebruiker** en verdeel de **Gebruikersnaam** van de **Eigenaar**. **cisco** wordt **hier** als **Gebruikersnaam gebruikt**.

System	stem 👻 Call Routing 👻 Media Resources 👻 Advanced Features 👻 Device 👻 Application 👻 User Management 👻 Bulk Administration 🎽 Help 👻							
Phone	Configuration			F	Related Links: Back To Find/List			
📄 s	we 🗙 Delete 📔 Copy 🎦 Reset 🧷 Apply Con	fig 🕂 Add New						
20	Need	Network Hold MOH Audio Source	2-ExternalSource	▼				
21	None	Location*	Hub_None	*				
22	None	AAR Group	< None >	*				
24	None	User Locale	English, United States	*				
25	None	Network Locale	< None >	~				
26	None	Built In Bridge*	Default	•				
27	None	Privacy*	Default	*				
28	None	Device Mobility Mode*	On	View Current Device Mobility Settings				
29	None	Owner	User Anonymous (Public/Shared Space)					
30	None	Owner User ID*	Cisco	T				
31	None	Mobility User ID	< None >	*				
32	None	Phone Personalization*	Default	*				

Stap 3. Zoals in de afbeelding, navigeer naar gebruikersbeheer > Eindgebruiker.

cisco	Cisco Unified CM Administration For Cisco Unified Communications Solutions				
System 👻	Call Routing - Media Resources - Advanced Features - Device - Application -	Us	er Management -Bulk Administration	•	Help 💌
			Application User		
A		\leq	End User		
	WARNING: No backup device is configured. This is requ		User/Phone Add	p	i in case of failure.
			SIP Realm		
Cisc	o Unified CM Administration		User Settings		
			Self-Provisioning		
System	version: 11.5.0.99838-4		Assign Presence Users		
VMware	: Installation: 4 vCPU Intel(R) Xeon(R) CPU E5-4669 v3 @ 2.10GHz, disl	k 1:	: 120Gbytes, 5120Mbytes RAM,	, Pi	artitions aligned
Jser c last l	ogged in to this cluster on Saturday, August 27, 2016 11:52:28 AM IST, to node 10.	106	5.99.199, from 10.196.120.156 using H	нт	ITPS
Copyright © All rights res	1999 - 2015 Cisco Systems, Inc. erved.				
This product	contains cryptographic features and is subject to United States and local country la stributors and users are responsible for compliance with U.S. and local country laws.	aws . By	governing import, export, transfer ar using this product you agree to com	and	I use. Delivery of Cisco cryptographic products does not imply third-party authority to impo ly with applicable laws and regulations. If you are unable to comply with U.S. and local laws

summary of U.S. laws governing Cisco cryptographic products may be found at our Export Compliance Product Report web site.

or information about Cisco Unified Communications Manager please visit our Unified Communications System Documentation web site.

or Cisco Technical Support please visit our <u>Technical Support</u> web site.

Zoek naar de gebruiker en selecteer de gebruiker die in Stap 2 aan de telefoon is toegewezen.

System 👻 Call	Routing 👻	Media Resources 👻	Advanced Features 👻	Device 💌	Application •	User Management 👻	Bulk Administratio	n 🕶 Help 🕶				
Find and List L	Jsers											
Add New	Select	All E Clear All	Delete Selected									
Status												
i 4 records	found											
liser (1 - 4	of 4)											Bow
Find User where	e First nam	e	▼ begins with ▼			Find Clear Filter	4 -					
	ı	Jser ID 📩	Meetin	g Number		First Name	L	ast Name	Department	Directory	URI	User Sta
\sim	<u>cisco</u>	>	3006				cisco2			cisco1@cisco.com		Enabled Local User
	cisco3		3001		А		Phone			cisco3@cisco.com		Enabled Local User
	cisco4		3002		В		Phone			cisco4@cisco.com		Enabled Local User

Bewaar de PIN van de gebruiker. Deze pin wordt gebruikt als u het Host van de vergadering bent.

System Call Routing	Media Resources • Advanced Features • Device • Ap	pplication 👻 User Management 👻 Bulk Administration 👻 Help 💌
End User Configuration		
🔚 Save 🗙 Delete 🗧	Add New	
-Status		
(i) Update successful		
-User Information		
User Status	Enabled Local User	
User ID*	cisco	
Password	•••••	Edit Credential
Confirm Password	•••••	
Self-Service User ID	3002	
PIN	•••••	Edit Credential
Confirm PIN		This is mantodatov to set the pin
Last name *	cisco2	
Middle name		
First name		
Display name		
Title		
Directory URI	cisco1@cisco.com	

Stap 4. Selecteer het selectieteken voor **Enable End-User to Host Conference Now**, zoals in het beeld:

Conference Now Information
Enable End User to Host Conference Now
Meeting Number 3002
Attendees Access Code 1234 This pin is used to join the participant in the conference.
Save Delete Add New

Verifiëren

Om uw configuratie te verifiëren, vraag om **Nu** van de **Conferentie** Aantal (DN) te **conferentie** (**3030**). Voer het vergadernummer **3002 in**, gevolgd door **#**key.

Als host houdt u de pin in stap 3 bij. Voor andere deelnemer deelt u nu het vergadernummer **3002** en de deelnemerscode **1234**.

Problemen oplossen

De stappen voor het oplossen van problemen bij deze configuratie worden in een afzonderlijk document behandeld.