

# E-Mail-Einstellungen für RV110W protokollieren

## Ziel

Der RV110W kann Systeminformationsprotokolle an ein E-Mail-Konto senden. Mit dieser Funktion kann ein Administrator über die Bedingungen des Routers auf dem Laufenden bleiben. In diesem Artikel wird erläutert, wie Sie die Einstellungen für das E-Mail-Protokoll auf der RV110W konfigurieren.

## Anwendbare Geräte

- RV110 W

## Verfahrensschritte

### E-Mail-Konfiguration protokollieren

Schritt 1: Wählen Sie im Router-Konfigurationsprogramm **Administration > Logging > Email Settings** aus. Die Seite *E-Mail-Einstellungen* wird geöffnet.

## E-mail Settings

### Log E-mail Configuration

E-mail Logs:

Enable

Minimum Email Log Severity:

Information

[Configure Severity](#)

E-mail Server Address:

E-mail Server Port:

(Range: 1 - 65535)

Return E-mail Address:

Send to E-mail Address (1):

Send to E-mail Address (2) (Optional):

Send to E-mail Address (3) (Optional):

E-mail Encryption (SSL):

Enable

Authentication with SMTP server:

None

E-mail Authentication Username:

E-mail Authentication Password:

E-mail Authentication Test:

[Test](#)

### Send E-mail Logs by Schedule

Unit:

Never

Day:

Sunday

Schritt 2: Aktivieren Sie rechts neben E-Mail-Protokolle das Kontrollkästchen **Aktivieren**, um Protokolle per E-Mail zu senden.

## E-mail Settings

### Log E-mail Configuration

E-mail Logs:	<input checked="" type="checkbox"/> Enable
Minimum Email Log Severity:	Information <a href="#">Configure Severity</a>
E-mail Server Address:	<input type="text"/>
E-mail Server Port:	<input type="text" value="25"/> (Range: 1 - 65535,
Return E-mail Address:	<input type="text"/>
Send to E-mail Address (1):	<input type="text"/>
Send to E-mail Address (2) (Optional):	<input type="text"/>
Send to E-mail Address (3) (Optional):	<input type="text"/>
E-mail Encryption (SSL):	<input type="checkbox"/> Enable
Authentication with SMTP server:	None ▾
E-mail Authentication Username:	<input type="text"/>
E-mail Authentication Password:	<input type="text"/>
E-mail Authentication Test:	<input type="button" value="Test"/>

### Send E-mail Logs by Schedule

Unit:	Never ▾
Day:	Sunday ▾

Schritt 3: Klicken Sie auf **Schweregrad konfigurieren**, um zu **Administration > Logging > Log Settings** zu wechseln, um die Protokolle für E-Mail zu konfigurieren.

**Hinweis:** Mit dieser Aktion werden Sie auf eine andere Seite umgeleitet und alle vorgenommenen Änderungen werden abgebrochen.

Schritt 4: Geben Sie im Feld E-Mail-Serveradresse eine E-Mail-Serveradresse ein, die den E-Mail-Adressen des Empfängers zugeordnet ist.

Schritt 5: Geben Sie im Feld E-Mail-Server-Port (E-Mail-Server-Port) die Portnummer des E-Mail-Diensteanbieters ein.

**Hinweis:** Wenn der E-Mail-Diensteanbieter keine spezielle Portnummer benötigt, lassen Sie die Standardnummer (25) im Feld.

Schritt 6: Geben Sie im Feld Retourenadresse (E-Mail-Adresse zurücksenden) eine E-Mail-Adresse ein, an die Protokollnachrichten gesendet werden, wenn die primären E-Mail-Adressen inaktiv sind.

Schritt 7: Geben Sie im Feld "E-Mail-Adresse senden" (1) die erste E-Mail-Adresse ein, die die Protokoll-E-Mail empfängt.

Schritt 8: Geben Sie im Feld An E-Mail-Adresse senden (2) (Optional) die zweite E-Mail-Adresse ein, die die Protokoll-E-Mail empfängt, wenn Sie möchten.

Schritt 9: Geben Sie im Feld An E-Mail-Adresse senden (3) (Optional) die dritte E-Mail-Adresse ein, die die Protokoll-E-Mail empfängt, wenn Sie möchten.

## E-mail Settings

### Log E-mail Configuration

E-mail Logs:	<input checked="" type="checkbox"/> Enable
Minimum Email Log Severity:	Information <a href="#">Configure Severity</a>
E-mail Server Address:	<input type="text" value="mail.mailserver.com"/>
E-mail Server Port:	<input type="text" value="25"/> (Range: 1 - 65535)
Return E-mail Address:	<input type="text" value="backup@mailserver.com"/>
Send to E-mail Address (1):	<input type="text" value="emai@mailserver.com"/>
Send to E-mail Address (2) (Optional):	<input type="text"/>
Send to E-mail Address (3) (Optional):	<input type="text"/>
E-mail Encryption (SSL):	<input type="checkbox"/> Enable
Authentication with SMTP server:	<input type="text" value="None"/>
E-mail Authentication Username:	<input type="text"/>
E-mail Authentication Password:	<input type="text"/>
E-mail Authentication Test:	<input type="button" value="Test"/>

### Send E-mail Logs by Schedule

Unit:	<input type="text" value="Never"/>
Day:	<input type="text" value="Sunday"/>

Schritt 10: Aktivieren Sie rechts neben E-Mail Encryption (SSL) das Kontrollkästchen **Aktivieren**, um E-Mails zu verschlüsseln.

## E-mail Settings

### Log E-mail Configuration

E-mail Logs:	<input checked="" type="checkbox"/> Enable
Minimum Email Log Severity:	Information <a href="#">Configure Severity</a>
E-mail Server Address:	<input type="text" value="mail.mailserver.com"/>
E-mail Server Port:	<input type="text" value="25"/> (Range: 1 - 65535,
Return E-mail Address:	<input type="text" value="backup@mailserver.com"/>
Send to E-mail Address (1):	<input type="text" value="emai@mailserver.com"/>
Send to E-mail Address (2) (Optional):	<input type="text"/>
Send to E-mail Address (3) (Optional):	<input type="text"/>
E-mail Encryption (SSL):	<input checked="" type="checkbox"/> Enable
Authentication with SMTP server:	<input type="text" value="None"/>
E-mail Authentication Username:	<input type="text"/>
E-mail Authentication Password:	<input type="text"/>
E-mail Authentication Test:	<input type="button" value="Test"/>

### Send E-mail Logs by Schedule

Unit:	<input type="text" value="Never"/>
Day:	<input type="text" value="Sunday"/>

Schritt 11: Wählen Sie im Dropdown-Menü Authentifizierung mit SMTP-Server den Authentifizierungstyp aus, den der E-Mail-Server verwendet.

Schritt 12: Wenn Sie None (Keine) auswählen, fahren Sie mit Schritt 12 fort. Wenn Sie eine andere Option auswählen, geben Sie den Benutzernamen für das E-Mail-Konto im Feld Benutzername für die E-Mail-Authentifizierung und das Kennwort für das Konto im Feld Kennwort für die E-Mail-Authentifizierung ein.

Minimum Email Log Severity:	Information	<a href="#">Configure Severity</a>
E-mail Server Address:	<input type="text" value="mail.mailserver.com"/>	
E-mail Server Port:	<input type="text" value="25"/>	(Range: 1 - 65535,
Return E-mail Address:	<input type="text" value="backup@mailserver.com"/>	
Send to E-mail Address (1):	<input type="text" value="email@mailserver.com"/>	
Send to E-mail Address (2) (Optional):	<input type="text"/>	
Send to E-mail Address (3) (Optional):	<input type="text"/>	
E-mail Encryption (SSL):	<input checked="" type="checkbox"/> Enable	
Authentication with SMTP server:	LOGIN	
E-mail Authentication Username:	<input type="text" value="email@mailserver.com"/>	
E-mail Authentication Password:	<input type="password" value="••••••••"/>	
E-mail Authentication Test:	<input type="button" value="Test"/>	
<b>Send E-mail Logs by Schedule</b>		
Unit:	Never	
Day:	Sunday	
Time:	12	AM
<input type="button" value="Save"/> <input type="button" value="Cancel"/>		

Schritt 13: Klicken Sie auf **Test**, um die E-Mail-Verbindung sofort zu testen.

Minimum Email Log Severity:	Information	<input type="button" value="Configure Severity"/>
E-mail Server Address:	<input type="text" value="mail.mailserver.com"/>	
E-mail Server Port:	<input type="text" value="25"/>	(Range: 1 - 65535,
Return E-mail Address:	<input type="text" value="backup@mailserver.com"/>	
Send to E-mail Address (1):	<input type="text" value="email@mailserver.com"/>	
Send to E-mail Address (2) (Optional):	<input type="text"/>	
Send to E-mail Address (3) (Optional):	<input type="text"/>	
E-mail Encryption (SSL):	<input checked="" type="checkbox"/> Enable	
Authentication with SMTP server:	LOGIN	
E-mail Authentication Username:	<input type="text" value="email@mailserver.com"/>	
E-mail Authentication Password:	<input type="password" value="••••••••"/>	
E-mail Authentication Test:	<input type="button" value="Test"/>	
<b>Send E-mail Logs by Schedule</b>		
Unit:	Never	
Day:	Sunday	
Time:	12	AM
<input type="button" value="Save"/> <input type="button" value="Cancel"/>		

Schritt 14: Klicken Sie auf **Speichern**, um die Änderungen zu speichern, oder auf **Abbrechen**, um sie zu verwerfen.

## E-Mail-Protokolle nach Zeitplan senden



Minimum Email Log Severity: Information

E-mail Server Address:  (f)

E-mail Server Port:  (Range: 1 - 65535, I)

Return E-mail Address:  (f)

Send to E-mail Address (1):  (f)

Send to E-mail Address (2) (Optional):

Send to E-mail Address (3) (Optional):

E-mail Encryption (SSL):  Enable

Authentication with SMTP server: LOGIN ▾

E-mail Authentication Username:

E-mail Authentication Password:

E-mail Authentication Test:

---

**Send E-mail Logs by Schedule**

Unit:  ▾

Day:  ▾

Time:  ▾

Never  
Hourly  
Daily  
Weekly

Schritt 1: Wählen Sie im Dropdown-Menü "Unit" (Einheit) aus, wie oft Sie die Protokoll-E-Mails empfangen möchten.

**Hinweis:** Wenn Sie Nie auswählen, werden keine Log-E-Mails gesendet.

Minimum Email Log Severity: Information

E-mail Server Address:  (F)

E-mail Server Port:  (Range: 1 - 65535, I)

Return E-mail Address:  (F)

Send to E-mail Address (1):  (F)

Send to E-mail Address (2) (Optional):

Send to E-mail Address (3) (Optional):

E-mail Encryption (SSL):  Enable

Authentication with SMTP server: LOGIN ▾

E-mail Authentication Username:

E-mail Authentication Password:

E-mail Authentication Test:

---

**Send E-mail Logs by Schedule**

Unit: Weekly ▾

Day: Sunday ▾  
Sunday  
Monday  
Tuesday  
Wednesday  
Thursday  
Friday  
Saturday

Time:

Schritt 2: Wählen Sie einen Wochentag aus dem Dropdown-Menü "Tag" aus, um die E-Mails zu erhalten.

Minimum Email Log Severity: Information

E-mail Server Address:

E-mail Server Port:  (Range: 1 - 65535)

Return E-mail Address:

Send to E-mail Address (1):

Send to E-mail Address (2) (Optional):

Send to E-mail Address (3) (Optional):

E-mail Encryption (SSL):  Enable

Authentication with SMTP server: LOGIN

E-mail Authentication Username:

E-mail Authentication Password:

E-mail Authentication Test:

---

**Send E-mail Logs by Schedule**

Unit:

Day:

Time:  AM

Schritt 3: Wenn Sie Wöchentlich oder täglich auswählen, wählen Sie aus den Dropdown-Menüs "Zeit" eine Tageszeit für den Empfang der E-Mails aus.

Schritt 4: Klicken Sie auf **Speichern**, um die Änderungen zu speichern, oder auf **Abbrechen**, um sie zu verwerfen.