# Consolidated Release Notes for Cisco WAE 7.2.1 and Patches

# Consolidated Release Notes for Cisco WAE 7.2.1 and Patches

#### **Contents**

- Introduction
- Release Information for Cisco WAE 7.2.1 Patch 1
- Install Cisco WAE 7.2.1 Patch 1
- Resolved Bugs
- Release Information for Cisco WAE 7.2.1
- What's New in Cisco WAE 7.2.1
- Upgrade to Cisco WAE 7.2.1
- Install and Configure Supervisor
- Verify WAE Image
- Install Cisco WAE
- Supported Node Versions
- Resolved Bugs
- Documentation
- Filing a Cisco WAE Bug
- Using the Cisco Bug Search Tool
- Accessibility Features

First Published: March 16, 2020

# Introduction

This document provides information regarding Cisco WAN Automation Engine (Cisco WAE) Release 7.2.1 and related patches.

Cisco WAN Automation Engine (WAE) provides the tools to create and maintain a model of the current network through the continual monitoring and analysis of the network and the traffic demands that are placed on it. This network model contains all relevant information about a network at a given time, including topology, configuration, and traffic information. You can use this information as a basis for analyzing the impact on the network due to changes in traffic demands, paths, node and link failures, network optimizations, or other changes.

The Cisco WAE platform is an open, programmable framework that interconnects software modules, communicates with the network, and provides APIs to interface with external applications.

This document contains the following topics:

- Release Information for Cisco WAE 7.2.1 Patch 1
- Release Information for Cisco WAE 7.2.1
- Documentation
- Filing a Cisco WAE Bug
- Using the Cisco Bug Search Tool
- Accessibility Features

# Release Information for Cisco WAE 7.2.1 Patch 1

This section provides information related to Cisco WAE Release 7.2.1 Patch 1 and contains the following topics:

- Install Cisco WAE 7.2.1 Patch 1
- Resolved Bugs

#### Install Cisco WAE 7.2.1 Patch 1

This procedure outlines the steps necessary to upgrade to Cisco WAE 7.2.1 Patch 1:

#### Before you begin

on the terminal like:

cp: cannot
stat ...

Download and verify the digitally signed Cisco WAE 7.2.1 Patch 1 image. See Verify WAE Image

#### **Procedure**

```
Step 1 Stop WAE services using supervisor.
       supervisorctl stop wae:*
Step 2 Change permission of the install file using the command:
       chmod 755 wae-linux-v7.2.1-patch1.bin
Step 3 Install Cisco WAE 7.2.1 Patch 1 using the following command:
       # ./wae-linux-v7.2.1-patch1.bin [-i WAE_INSTALL_DIR] [-r WAE_RUN_DIR] [-b BACKUP_DIR]
       WAE_INSTALL_DIR is the WAE install directory path.
       WAE_RUN_DIR is the run directory path.
       BACKUP_DIR is the backup directory to use when creating the patch.
         During the
         backup
         phase of
         WAE
       Ninstallation.
       o you may
       t see a few
       e messages
```

This is expected and does not cause any problems with the patch install.

**Step 4** Start WAE services using supervisor:

supervisorctl start wae:\*

**Step 5** Confirm that all WAE services are running:

supervisorctl status

Step 6 On the WAE CLI, run:

admin@wae# packages reload

After installation of the patch, use the new version of Cisco WAE Design (WAE-Design-k9-7.2.1-patch1-

NLinux-x86\_64.signed.bin) that is available for download

for all platforms. Verify the signed image before

installing. See Cisco WAE Design 7.2.1 GUI Installation

Guide.

e After applying Cisco WAE 7.2.1 Patch 1, a few error messages are captured in the java log files. These error messages can be safely ignored and no WAE functionality is affected.

Step 7 (Optional) If license\_install tool was run previously from within the WAE install directory <WAE INSTALL DIR>, then run the license install tool once again after installing this patch.

# **Resolved Bugs**

The following are descriptions of the resolved bugs in Cisco WAE Release 7.2.1 Patch 1:

Table 1. Resolved Bugs

Bug ID	Description
1	Unable to collect inventory for Huawei VRP 5 and CPU/MEM for VRP 8
CSCvs5215 5	VPN traffic measured not populated
	Aggregation of network demand hangs preventing any further aggregation from running
CSCvs9513 2	DNF Netflow NIMO throws "java.lang.NullPointerException" error during nimo execution
5	In WAE 7.2.1, IP address information is lost from Interfaces table after DARE aggregation
	In WAE 7.2.1, Optical NIMO creates too many files in /tmp
CSCvs5873 5	login-find-multicast-nimo fails with "Python cb_action" error
CSCvs5942 2	Unable to change enabled field from config UI
CSCvs6876	Intermittent DARE aggregation error and failure

7	
	Virtual nodes shown as type physical
	In WAE 7.2.1, cisco-wae-archive fills the wae-python-vm.log
	WAE 7.1.2 to WAE 7.2.1 upgrade migraton script fails
	In WAE 7.1.3 Patch 3, Isp-snmp-nimo is shown as as Unrouted
	WAE does not resolve interface name on IPv6 ALU devices
CSCvs9544 5	In WAE 7.1.3 Patch 3, cfg_parse timeout occurs when traffic-poller begins/is running
8	Update/Return license reservation APIs throw "classcast exception" error after agent restart
CSCvs2933 5	Layout NIMO does not copy SRLGs from the template

# **Release Information for Cisco WAE 7.2.1**

This section provides information related to Cisco WAE Release 7.2.1 and contains the following topics:

- What's New in Cisco WAE 7.2.1
- <u>Upgrade to Cisco WAE 7.2.1Install and Configure SupervisorVerify WAE ImageInstall Cisco</u> WAE
- Supported Node Versions
- Resolved Bugs

#### What's New in Cisco WAE 7.2.1

The following features are new in Cisco WAE 7.2.1

Feature	Description
Smart Licensing	Cisco WAE now supports both Cisco Smart Licensing and traditional licensing. Cisco Smart Licensing is a standardized licensing platform that enables you to automate time consuming manual licensing tasks, track the status of your license and software usage trends.  Some of the benefits that Cisco Smart Licensing offers are:  • Visibility to devices and software purchased and deployed  • Ability to monitor and manage devices, licenses, and usage in real time  • Automatic license activation  • Product simplicity with standard software offers, licensing platform, and policies  • Decreased operational costs  WAE UI Smart Licensing is added to enable you to configure and manage all details related to smart licenses.  For more information, see "Cisco Smart Licensing" chapter in the Cisco WAE 7.2.1 User Guide.
III	Cisco WAE now supports High Availability (HA) with automatic failover. If a
failover	primary node fails, the secondary node takes over as Master node.

	WAE UI HA configuration page is updated to enable you to configure master	
	and slave nodes.	
	For more information, see "Administration" chapter ("Configure High	
	Availability" topic) in the Cisco WAE 7.2.1 User Guide.	
	Cisco WAE now comes with embedded online help. Use the Help button on	
	WAE UI to access the related help topics.	
Online Help	Documents are sometimes undated after original publication. Refer	to th
	Note  Cisco WAE 7.2.1 User Guide document on Cisco.com for latest updated and original publication. Reference to the control of the control o	
	The Changeover tool is enhanced to allow you to group Interface Metric	
	changes together into steps. You can:	
Changeover tool	Group parallel interfaces metric changes together.	
enhancements	Group interface metric changes from the same source if there is no	
o mano o monto	impact to maximum utilization.	
	For more information, see "Changeover" chapter ("Running the Changeover	
	Tool" topic) in the Cisco WAE Design 7.2.1 User Guide.	
	SR policy is enhanced to support multiple candidate path along with	
Enhancement to	preference.	
SR policy	If an SR LSP contains multiple SR Candidate paths, the demand is routed on	
modelling to	the LSP path with the highest preference option for which the demand can be	
support multiple	routed from source to destination.	
candidate path	For more information, see "Segment Routing Simulation" chapter ("SR LSP	
candidate patri	Routing" topic) in the Cisco WAE Design 7.2.1 User Guide.	
	In Cisco WAE Design, the RSVP-TE Optimization Tool is enhanced to allow	
DOVED TE	you to set avoidance constraints.	
RSVP-TE	Navigate to Tools RSVP LSP Optimization RSVP-TE Opt. Avoid Objects	
Optimization Tool	section in the Advanced tab lets you to select Nodes, Interfaces, L1 Links, L1	
enhancemets	Nodes, SRLGs to be avoided when optimizing LSPs.	
	For more information, see "RSVP-TE Optimization" chapter ("Optimization	
	Input" topic) in the Cisco WAE Design 7.2.1 User Guide.	
	Cisco WAE Live database management now provides you with the following	
	options:	
WAE Live	Manage database space by the age of the record.	
Database	Manage database space by the % of the disk capacity.	
management	The dependency on Oracle Java is also removed.	
	For more information, see "Performing Administrative Tasks" chapter	
	("Database Management" topic) in the Cisco WAE Live 7.2.1 User Guide.	
la cantan data	On WAE Live Inventory page, the Table view is updated to include Last	
Inventory data	Collected field at the bottom of the page which displays the date and time of	
collection	last collected data.	
timestamp	For more information, see "Viewing Inventory" chapter ("Viewing the	
	Inventory Table" topic) in the Cisco WAE Live 7.2.1 User Guide.	
	Cisco WAE software (including WAE Design and WAE Live) now come with	
	digital signatures. The verifiable digital signatures ensure that the Cisco WAE	
Digital Signing	software running on your systems is secure and has not been tampered with,	
Digital Signing	and that the software originated from a trusted source.	
	For more information, see Cisco WAE 7.2.1 Installation Guide and Cisco	
	WAE Design 7.2.1 GUI Installation Guide.	
Enhancement to		
SR policy		
modelling to	Cisco WAE is now updated to support additional SID types - Interfaces,	
support multiple	Nodes, Node Groups, LSPs.	
SID type		

Cisco WAE	WAE is now enhanced to support 3000 nodes for modeling, simulation and		
scaling	optimization.		
EPNM 3.0 support			
for optical	WAE now supports EPNM 3.0 with NCS2K (11.0/11.1).		
collection			
WAE performance	NIMOs are now enhanced to support native format.		
improvements	NilviOs are now enhanced to support native format.		
Inter AS BGP	AS-merge is enhanced to handle dropped demands.		
ennancement			
WMD - Increase in	Performance of WMD interacting with SAGE is improved.		
robustness	Fertormance of wivid interacting with SAGE is improved.		

### **Upgrade to Cisco WAE 7.2.1**

Follow the below workflow to install or upgrade to Cisco WAE 7.2.1:

- Install and Configure Supervisor
- Verify WAE Image
- Install Cisco WAE

#### **Install and Configure Supervisor**

Install and configure supervisor before installing WAE.

The following configuration steps work only when supervisor is installed using yum. If Nsupervisor is o installed t using any e other method, it has to be configured to run supervisorctl as a non root user.

#### **Procedure**

#### Step 1 Install supervisor and verify.

```
sudo yum install -y epel-release sudo yum install -y supervisor supervisord -version 3.1.4\,
```

Step 2 Create directories with write permissions for the OS user running WAE.

sudo mkdir -p /opt/supervisor/run sudo mkdir -p /opt/supervisor/log sudo chown -R [USER-NAME]:[GROUP-NAME] /opt/supervisor

# **Step 3** Update supervisor configuration to not run as a root user. Point the pid file to /opt/supervisor/run/supervisor.pid and user as the OS user running WAE.

Open /etc/supervisord.conf as root and edit.

• In the [unix\_http\_server] section:- Change

;file=/var/run/supervisor/supervisor.sock to

file=/opt/supervisor/run/supervisor.sock- Change

;chown=nobody:nogroup to chown=[USER-NAME]:[GROUP-NAME]

• In the [supervisord] section:- Change

;logfile=/var/log/supervisor/supervisord.log to

logfile=/opt/supervisor/log/supervisord.log.- Change

;pidfile=/var/run/supervisord.pid to

pidfile=/opt/supervisor/run/supervisord.pid- Change ;minfds=1024

to minfds=1000000- Change; minprocs=200 to minprocs=257805

In the [supervisorctl] section:- Change

;serverurl=unix:///var/run/supervisor/supervisor.sock to
serverurl=unix://opt/supervisor/run/supervisor.sock

#### Step 4 Start Supervisor.

sudo systemctl start supervisord supervisorctl status all

**Step 5** Enable supervisor to start during system startup.

sudo systemctl enable supervisord sudo systemctl status supervisord

#### **Verify WAE Image**

#### **Procedure**

- **Step 1** Download the Cisco WAE 7.2.1 software package from Cisco Download Software site.
- **Step 2** The certificate and digital signature are both embedded in the downloaded file wae-linux-v7.2.1.signed.bin.

**Step 3** Run the self-extracting signed binary. This extracts the Release Binary and validates using the signature file. Verification of signed image

[admin@wae-vm-21 workspace.signed]\$ ./wae-linux-v7.2.1.signed.bin Unpacking... Verifying signatu Downloading CA certificate from http://www.cisco.com/security/pki/certs/crcam2.cer ... Successful downloaded and verified crcam2.cer. Downloading SubCA certificate from http://www.cisco.com/security/pki/certs/innerspace.cer ... Successfully downloaded and verified innerspace.cer. Successfully verified root, subca and end-entity certificate chain. Successfully

fetched a public key from WAE-CCO\_RELEASE.cer. Successfully verified the signature of wae-linux-

v7.2.1.bin using WAE-CCO\_RELEASE.cer **Step 4** The generated wae-linux-v7.2.1.bin is the Linux installer for WAE.

#### **Install Cisco WAE**

#### Before you begin

• If one does not yet exist, create a UNIX user (assigned to a group). You must be this UNIX user to run installation.

- Make sure supervisor is installed and configured. See Install and Configure Supervisor.
- Download and verify the digitally signed Cisco WAE 7.2.1 image. See Verify WAE Image.
- Make sure Java-8 is installed on the system and JAVA\_HOME environment variable is pointing to jdk-1.8.
- Make sure that requests.auth python package is installed for the BW-OPT application to function in WAE.
- For migrating the existing 7.1.x configurations to 7.2.1 please go through the README file provided with "Cisco WAE upgrade script for migrating configurations from WAE 7.1.x to WAE 7.2.1" package from CCO.

#### **Procedure**

Step 1 Stop WAE if running.

**Step 2** Change permission of the install file using the command:

chmod +x wae-linux-v7.2.1.bin

**Step 3** Run the installer specifying the target directory.

./wae-linux-v7.2.1.bin <wae-dir>

**Step 4** Setup environment and create a runtime directory specifying the path.

cd <wae-dir> source waerc wae-setup --dest <target-runtime-dir>

**Step 5** You are prompted to set the Cisco WAE admin password.

WAE admin password: Confirm password:

**Step 6** After installing and setting up wae (i.e. after running wae-setup), create a soft link to the wae.ini fil from inside /etc/supervisord.d/ and add WAE config to supervisor.

sudo ln -sf <target-runtime-dir>/wae.ini /etc/supervisord.d/

Execute

Nthis step

only after

t supervisor

e is installed

and

configured.

**Step 7** Update supervisor configuration.

supervisorctl update

#### Step 8 Start WAE process

supervisorctl start wae:\* wae:zookeeper: started wae:waectl: started wae:kafka: started wae:waemonitor: started

Ν

0

t

е

#### Step 9 Check status of WAE process

supervisorctl status wae:kafka RUNNING pid 1540, uptime 28 days, 14:03:40 wae:logrotate RUNNING 1178, uptime 28 days, 15:10:11 wae:wae-monitor RUNNING pid 11520, uptime 0:00:12 wae:waectl RUNN pid 1177, uptime 28 days, 15:10:11 wae:zookeeper RUNNING pid 1736, uptime 28 days, 14:03:39

NTo stop all

o WAE

t process, use

e the

command:

# **Supported Node Versions**

The following table lists the supported node versions for Cisco WAE 7.2.1

Table 2. Supported Node Versions for Cisco WAE 7.2.1

Feature	Product	Tested with version	Notes
SRTM	IOS-XR	6.6.2 + SMU, 6.5.3 + SMU	
	IOS-XR	ומאו	NED Version: ncs-4.7.4-cisco-iosxr-7.11.1
Netconf LSP	IOS-XR	1153	NED Version: ncs-4.7.4-cisco-ios-6.22.1
	Juniper Junos Mx960	18.1R1.9	NED Version: ncs-4.7.1-juniper- junos-4.1
RT Apps, Multi XTC, Reactive polling.	IOS-XR	6.6.2 + SMU, 6.5.3 + SMU	
Multilayer	NCS2K	10.9, 11.0	
	EPNM	3.0.3	

# **Resolved Bugs**

The following are descriptions of the resolved bugs in Cisco WAE Release 7.2.1:

Table 3. Resolved Bugs

	Description
	Running topo-vpn-nimo to discover L3 and L2 VPNs in a network results in error.
CSCvp6052 0	Unable to keep active connection with XTC.
CSCvp6280 3	WMD does not get traffic from traffic-poll-nimo.
CSCvq3467 2	rpc-error occurs on downloading .pln file from WMD using WAE-Design.
CSCvq3641 3	'Traffic fitting failed error' message displayed during Demand Deduction.
CSCvq5472 5	Interfaces with Util Sim higher than 100% due to demands coming from netflow.
CSCvq5975 5	'Bad file descriptor' error message is displayed when external-executable-nimo is executed.
CSCvq7019 0	zookeperctl.out file is filled up with a lot of messages.
	WAE High Availability does not work as expected.
CSCvq7948 8	Java Exception in topo-igp - Out Of Memory.

•	WAE XTC agent keeps multiple connections with XTC and is not consuming the information sent by XTC, increasing XTC memory usage.
	topo-bgp-nimo collection is unable to complete the upload to CDB due to "Invalid
2	Value error for peer-id.
CSCvr0935 7	traffic-demands-nimo is not executed at regular intervals and at times it is not executed correctly.
CSCvr1225	The final network model does not have the layout coming from layout-nimo. It gets
2	corrupted.
CSCvr8531 7	The DARE aggregation fails after few hours.
CSCvr8622 5	wae.log captures many CRIT errors showing instabilities in the processes and results in WAE restarting. /tmp folder get filled upto 100% when topo-vpn-nimo is executed.
CSCvm340 65	DARE does not process changes, displays 'Queue full' error message.
CSCvm572 53	Packages reload when simultaneous collections are scheduled.
	Following error is seen while loading plan file with L1 and L3 information:
CSCvn4916 0	wae@wae# wae components load-plan run plan-file /home/wae/bonn-agg_v30.pln network-name bonn-archive Error: Python cb_action error. external error (19): Error on line 588: unknown
	element: dispaly-name
CSCvo7848 0	DARE rebuild creates another DARE network when one network gets sourced to multiple DARE network.
1	The traffic balance of external endpoint member is rounded off when a plan file is imported.
CSCvq2675 3	WAE DARE does not consolidate NIMOs when node-filter configuration is changed
0	inter-as-nimo deletes ASes previously merged from newly merged plan files that are not related to the other merges.
CSCvq3910 2	login_test and snmp_test loois are not packaged with WAE collector.
CSCvq5320 5	Supervisorct1 THE HMITS NEED TO DE INCLEASED AT INSTAIL TIME.
CSCvq5429 8	WAE is unable to discover Huawei CX600 boxes and hardware inventory
CSCvq5690 6	Intermittent Failures while writing plan files to Archives.
CSCvr5138 5	Maximum opened files option in netflow agent or flow collector tools is always set to 4096 when WAE is started using supervisorctl.
CSCvr8476 0	Kafka issue impacting multiple components.
CSCvp4431	WAE Design application is slow to recompute simulated traffic numbers when the
0	Multicast tables are included.
CSCvq5763 4	On WAE Design, Save to -> Template option must be enhanced to allow the operator to update layout-nimo template file directly to WAE Server.
CSCvq8475 9	Introduce NetIntHistory details in the output plan file.
CSCvr2430 3	On WAE Design, introduce Save option to WAE server to improve performance.
_	When trying to execute run-config-parse, WAE fails with illegal reference error for
-	

4

p2mp-lsp-name.

### **Documentation**

To find descriptions of all related Cisco WAE documentation, see <u>Documentation Roadmap</u>.

We sometimes update the documentation after original upublication.

Therefore, you

- o therefole, you
- t should always
- e review the documentation on Cisco.com for any updates.

# Filing a Cisco WAE Bug

While filing CDETS for Cisco WAE, make sure the following information is captured:

- WAE configuration: supervisord configuration, aggregator configuration and the nimo configuration of concerned network and its source-network, if any.
- <run-dir>/logs/ directory
- Plan file(s) for the network(s) of concern
- <run-dir>/data/stats/ for system stability and resource usage related issues
- <run-dir>/work/dare/ for aggregation related issues.
- <run-dir>/data/networks/\*.db for issues related to networks configured as 'native' and the corresponding aggregator (final-network).
- CDB dump of the networks of concern for networks of 'yang' format ('yang' is the default storage-format).
- Configuration corresponding to the component of concern. Eg: WMD, archive etc.
- For collection issues, record file(s) if the nimo supports record-playback.
- ~/.cariden/logs/ for designapid related issues.

# **Using the Cisco Bug Search Tool**

You can use the Cisco Bug Search Tool to search for a specific bug or to search for all bugs in a release.

#### **Procedure**

The Bug Search page opens.

Note that the bug Search page opens.

If you do not have a Cisco.com username and password, you can the bug Search page opens.

the bug Search page opens.

If you do not have a Cisco.com username and password, you can the bug Search page opens.

Step 3 Use any of these options to search for bugs, and then press Enter (Return) to initiate the search:
To search for a specific bug, enter the bug ID in the Search For field.

- To search for bugs based on specific criteria, enter search criteria, such as a problem descrip a feature, or a product name, in the Search For field.
- To search for bugs based on products, enter or select a product from the Product list. For exa if you enter "WAE," you get several options from which to choose.
- To search for bugs based on releases, in the Releases list select whether to search for bugs
  affecting a specific release, bugs that were fixed in a specific release, or both. Then enter one
  more release numbers in the Releases field.

**Step 4** When the search results are displayed, use the filter tools to narrow the results. You can filter the by status, severity, and so on. To export the results to a spreadsheet, click Export Results to Excel.

# **Accessibility Features**

For a list of accessibility features in Cisco WAE, visit <a href="https://www.cisco.com/c/en/us/about/accessibility/voluntary-product-accessibility-templates.html">https://www.cisco.com/c/en/us/about/accessibility/voluntary-product-accessibility-templates.html</a> (VPAT) website, or contact accessibility@cisco.com.

All product documents except for images, graphics, and some charts are accessible. If you would like to receive the product documentation in audio format, braille, or large print, contact accessibility@cisco.com.